


TOPOLOGY



Router Config

```
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int e0/0
R1(config-if)#ip add 50.0.0.1 255.0.0.0
R1(config-if)#no sh
R1(config-if)#int e0/1
R1(config-if)#ip add 172.16.0.1 255.255.0.0
R1(config-if)#no sh
R1(config-if)#exit
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.10
R1(config)#ip route 192.168.2.0 255.255.255.0 172.16.0.2
R1(config)#ip dhcp pool SALES
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.10
R1(config)#exit
R1#
```

```
R2
R2(config)#int e0/0
R2(config-if)#
*Jul 29 07:55:34.867: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to do
wn
*Jul 29 07:55:34.872: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to do
wn
*Jul 29 07:55:35.869: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to down
*Jul 29 07:55:35.874: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to down
R2(config-if)#ip add 192.168.2.1 255.255.255.0
R2(config-if)#no sh
R2(config-if)#int e0/1
R2(config-if)#ip add 172.16.0.2 255.255.0.0
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#ip route 50.0.0.0 255.0.0.0 172.16.0.1
R2(config)#int e0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#exit
R2(config)#
*Jul 29 08:00:24.558: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Confi
g Wizard)
R2(config)#
```

172

192.168.2.1

eth0

VPC-4

IP Assigned For HR Depart

```
VPC-1

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.0.11/8 GW 50.0.0.1

VPC-1> █
```

```
VPC-2

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.12/8 GW 50.0.0.1

VPC-2> █
```



IP Assigned for Sales Depart

```
VPC-4
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4> ip dhcp
DDD
Can't find dhcp server

VPC-4> ip dhcp
DDORA IP 192.168.2.11/24 GW 192.168.2.1

VPC-4> █
```

QEMU (Win)

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
<C> Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

 Connection-specific DNS Suffix . :
 IP Address : 192.168.2.12
 Subnet Mask : 255.255.255.0
 Default Gateway : 192.168.2.1

C:\Documents and Settings\user>_

Start

Putty

Tftpd32

C:\WINDOWS\system...

9:01 AM