REVIEW AND PRACTICE PRACTICAL

1. Open Cisco Packet Tracer and create a new project file named 'HomeWiFiNetwork.pkt' with three PCs and one wireless router connected appropriately.

Steps:

1. Open **Cisco Packet Tracer** and create a new project.
2. Add **one wireless router** to the workspace.
3. Add **three PCs** to the workspace.
4. Connect the PCs to the wireless router using Wi-Fi, if the PCs support wireless connections. Otherwise, use Ethernet cables.
5. Configure the router's SSID and Wi-Fi password.
6. Assign IP addresses to all three PCs using DHCP.
7. Save the project as **HomeWiFiNetwork.pkt**.

2. Assign static IP addresses to each PC in your Packet Tracer network so they are on the same subnet (e.g., 192.168.10.x), and configure the default gateway to the router's IP.
Steps:

1. Click **PC0 → Desktop → IP Configuration**.
2. Select **Static** and enter:
    - IP Address: 192.168.10.2
    - Subnet Mask: 255.255.255.0
    - Default Gateway: 192.168.10.1
3. Configure **PC1**:
    - IP Address: 192.168.10.3
    - Subnet Mask: 255.255.255.0
    - Default Gateway: 192.168.10.1
4. Configure **PC2**:
    - IP Address: 192.168.10.4
    - Subnet Mask: 255.255.255.0
    - Default Gateway: 192.168.10.1
5. Ensure the router's LAN IP address is 192.168.10.1.

3.Test connectivity by using the Packet Tracer 'ping' tool to verify that all PCs can communicate with each other and the router.

Hint: Use the Command Prompt tool on each PC and type 'ping [other PC's IP]'.

Steps:

1. Click **PC0 → Desktop → Command Prompt**.
2. Type ping 192.168.10.3 to test connectivity with PC1.
3. Type ping 192.168.10.4 to test connectivity with PC2.
4. Type ping 192.168.10.1 to test connectivity with the router.
5. Repeat the ping tests from other PCs.

4.Document each step you took to build and configure your Packet Tracer network, including screenshots of your topology and the IP configuration windows for each PC, in a Word or PDF file.

1. **Network Topology** — one wireless router and three PCs.
2. **PC0 IP Configuration** — 192.168.10.2
3. **PC1 IP Configuration** — 192.168.10.3
4. **PC2 IP Configuration** — 192.168.10.4
5. **Ping Test** — successful connectivity between PCs and the router.

The default gateway for all three PCs should be 192.168.10.1, with subnet mask 255.255.255.0.