Module 3


Installing Web Server (IIS) and Print Document Services Roles

Apply the configuration in UST-DC

Installing the Web Server (IIS) role

To install the **Web Server (IIS)** role in Windows Server 2022, follow these steps:

1. Click the **Start** button. Then, in the **Start** menu, click **Server Manager**.
2. Click on the **Add roles and features** hyperlink in the **Server Manager** window.
3. Shortly, the **Add Roles and Features Wizard** area will open, as shown in the following screenshot:




4. Accept the **Role-based or feature-based installation** option and click **Next**.
5. Ensure that the correct server is highlighted from the server pool. Then, accept the **Select a server from the server pool** option and click **Next**.
6. Select the **Web Server (IIS)** role from the list of roles.
7. Click the **Add Features** button when the **Add features required for Web Server (IIS)** popup appears.
8. No feature is required to add the **Web Server (IIS)** role at this stage, so click **Next**.
9. In the **Web Server (IIS)** definition and the things to note regarding installing **Web Server (IIS)**, click **Next**.
10. Either accept the **Web Server (IIS)** role services or customize them to your needs.
11. Confirm your installation selections for the **Web Server (IIS)** role by clicking the **Install** button.
12. When the installation completes, click the **Close** button to close the **Add Roles and Features Wizard** area.
13. With that, the **Web Server (IIS)** role will be installed. A server restart is not required.

Installing a PDS role


To install a **Print and Documents Service** role in Windows Server 2022, follow these steps:

1. Click the **Start** button. Then, in the **Start** menu, click **Server Manager**.
2. Click on the **Add roles and features** hyperlink in the **Server Manager** window.
3. Shortly, the **Add Roles and Features Wizard** area will open.
4. Accept the **Role-based or feature-based installation** option and click **Next**.
5. Ensure that the correct server is highlighted from the server pool. Then, accept the **Select a server from the server pool** option and click **Next**, as shown in the following screenshot:


Add Roles and Features Wizard
Select destination server
DESTINATION SERVER
Dautti-Server01.Dautti.local
Before You Begin
Installation Type
Server Selection
Server Roles
Features
Confirmation
Results
Select a server or a virtual hard disk on which to install roles and features.
Select a server from the server pool
Select a virtual hard disk
Server Pool
Filter:
Name
IP Address
Operating System
Dautti-Server01.Dautti.lo...
169.254.207.48...
Microsoft Windows Server 2022 Datacenter
1 Computer(s) found
This page shows servers that are running Windows Server 2012 or a newer release of Windows Server, and that have been added by using the Add Servers command in Server Manager. Offline servers and newly-added servers from which data collection is still incomplete are not shown.
< Previous
Next >
Install
Cancel

6. From the list of roles, select the **Print and Document Services** role.
7. Click the **Add Features** button when the **Add features that are required for Print and Document Services** dialog box pops up.
8. At this stage, no feature is required to add a PDS role, so click **Next**.
9. In the PDS definition and the things to note regarding PDS installation, click **Next**.
10. Either accept the PDS role services or customize them to your needs.
11. Confirm the installation selections for the PDS role by clicking the **Install** button.
12. When the installation completes, click the **Close** button to close the **Add Roles and Features Wizard** area.


With that, the PDS role will be installed. A server restart is not required.



In UST-A VM:


1. Open an Edge Browser, then Type 10.10.10.10 at the address field

2. You must be able to view the default webpage of the Web Server in UST-DC




In UST-DC VM:

- On the Server Manager, click on Tools and select Internet Information Services (IIS) Manager




In UST-DC VM:

- On Internet Information Services (IIS) Manager, select UST-DC and then select Default Document.




In UST-DC VM:

- On Internet Information Services (IIS) Manager – Default Document, a list of default webpages are visible



In UST-DC VM:


- Open a File explorer, and type in the following on the address field, C:\inetpub\wwwroot – (location of the default webpage)



Creating a simple webpage:

In UST-DC VM:


- On the file explorer type the location C:\inetpub\wwwroot
- Right click New – Text Document



Creating a simple webpage:

In UST-DC VM:


- Create a simple webpage (as seen on the image)
- save as “sample.html”



Creating a simple webpage:

In UST-DC VM:

- Go back to IIS Manager, on the Action Pane, select Add.
- Type sample.html on the text field and click Ok.
- Make sure that the sample.html is on top of the list



Creating a simple webpage:

In UST-A VM:

- Open an Edge browser and type 10.10.10.10 on the address field. You should be able to access the sample.html.

For the Activity:

Create a webpage that contains information about yourself (Hobbies, Collections, Favorite Places, etc) in UST-DC. This should be accessible to UST-A

If you need to access the internet to get images and designs, change the following settings temporarily:

1. Virtual Box Manager – change settings of the Network from Internal Network to NAT
2. UST-DC VM – change the “Ethernet” adapter – select “Obtain an IP address Automatically” and “Obtain DNS server address automatically”(make sure to remember the network configurations), You should be able to access the internet at this time.

For access of finish webpage, revert back all the network settings.