

CONFIGURACION DEL ROUTER R1-AD

ME OLVIDE SACAR CAPTURA :'(

Configuracion del sw:

```
Switch#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#hostname SW
SW(config)#vlan 10
SW(config-vlan)#name REDES
SW(config-vlan)#exit
SW(config)#vlan 20
SW(config-vlan)#name ADMIN
SW(config-vlan)#exit
SW(config)#interface FastEthernet0/10
SW(config-if)#switchport mode access
SW(config-if)#switchport access vlan 20
SW(config-if)#exit
SW(config)#
SW(config)#interface FastEthernet0/11
SW(config-if)#switchport mode access
SW(config-if)#switchport access vlan 20
SW(config-if)#exit
SW(config)#
SW(config)#interface FastEthernet0/12
SW(config-if)#switchport mode access
SW(config-if)#switchport access vlan 20
SW(config-if)#exit
SW(config)#interface FastEthernet0/1
SW(config-if)#switchport mode trunk

SW(config-if)#exit
SW(config)#
SW(config)#interface FastEthernet0/2
SW(config-if)#switchport mode trunk

SW(config-if)#exit
```

Configuracion del sw - ad:

```
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#hostname SW-AD
SW-AD(config)#vlan 10
SW-AD(config-vlan)#name REDES
SW-AD(config-vlan)#exit
SW-AD(config)#vlan 20
SW-AD(config-vlan)#name ADMIN
SW-AD(config-vlan)#exit
SW-AD(config)#interface FastEthernet0/20
SW-AD(config-if)#switchport mode access
SW-AD(config-if)#switchport access vlan 10
SW-AD(config-if)#exit
SW-AD(config)#
SW-AD(config)#interface FastEthernet0/21
SW-AD(config-if)#switchport mode access
SW-AD(config-if)#switchport access vlan 10
SW-AD(config-if)#exit
SW-AD(config)#
SW-AD(config)#interface FastEthernet0/22
SW-AD(config-if)#switchport mode access
SW-AD(config-if)#switchport access vlan 10
SW-AD(config-if)#exit
SW-AD(config)#interface FastEthernet0/2
SW-AD(config-if)#switchport mode trunk
SW-AD(config-if)#exit
SW-AD(config)#
SW-AD(config)#exit
SW-AD#write memory
%SYS-5-CONFIG_I: Configured from console by console
```

configurar el servidor http:

HTTP

Physical

Config

Services

Desktop

Programming

Attributes

IP Configuration

IP Configuration

☐ DHCP

☒ Static

IPv4 Address

222.0.0.2

Subnet Mask

255.255.255.248

Default Gateway

222.0.0.1

DNS Server

222.0.0.4

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

/

Link Local Address

FE80::20A:F3FF:FEA1:C8EA

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication

MD5

Username

Password

servidor dns:

DNS

Physical Config Services **Desktop** Programming Attributes

IP Configuration X

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 222.0.0.4

Subnet Mask 255.255.255.248

Default Gateway 222.0.0.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::20C:CFFF:FE9C:68C7

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

servidor ftp:

FTP

PhysicalConfigServicesDesktopProgrammingAttributes

IP Configuration

X

IP Configuration

DHCP

Static

IPv4 Address

222.0.0.5

Subnet Mask

255.255.255.248

Default Gateway

222.0.0.1

DNS Server

222.0.0.4

IPv6 Configuration

Automatic

Static

IPv6 Address

/

Link Local Address

FE80::201:97FF:FED9:B8E1

Default Gateway

DNS Server

802.1X

Use 802.1X Security

Authentication

MD5

Username

Password

pc5:

The screenshot shows a configuration window for a device labeled 'PC5'. The window has a title bar with standard minimize, maximize, and close buttons. Below the title bar are four tabs: 'Physical', 'Config', 'Desktop' (which is selected), and 'Programming'. The 'Desktop' tab contains a sub-tab labeled 'IP Configuration' with a close button 'X'. Under this sub-tab, the 'Interface' is set to 'FastEthernet0'. The 'IP Configuration' section has two radio buttons: 'DHCP' (unselected) and 'Static' (selected). Below these are four text input fields: 'IPv4 Address' with the value '222.0.0.18', 'Subnet Mask' with '255.255.255.240', 'Default Gateway' with '222.0.0.17', and 'DNS Server' with '222.0.0.4'. The 'IPv6 Configuration' section also has two radio buttons: 'Automatic' (unselected) and 'Static' (selected). It includes four text input fields: 'IPv6 Address' (empty), 'Link Local Address' with the value 'FE80::201:63FF:FE30:6EC0', 'Default Gateway' (empty), and 'DNS Server' (empty). The '802.1X' section has a checkbox 'Use 802.1X Security' which is unchecked. Below it is a dropdown menu for 'Authentication' set to 'MD5', and two empty text input fields for 'Username' and 'Password'.

PC5

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 222.0.0.18

Subnet Mask 255.255.255.240

Default Gateway 222.0.0.17

DNS Server 222.0.0.4

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::201:63FF:FE30:6EC0

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

pc7:

PC7

Physical Config Desktop Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 222.0.0.20

Subnet Mask 255.255.255.240

Default Gateway 222.0.0.17

DNS Server 222.0.0.4

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::260:5CFF:FEA9:EC6A

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

pc9:

PC9

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 222.0.0.22

Subnet Mask 255.255.255.240

Default Gateway 222.0.0.17

DNS Server 222.0.0.4

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::205:5EFF:FEDB:2D7D

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Conexiones:



porcentaje conectado:

 PT Activity: 01:54:55

— □ ×

Realiza las configuraciones necesarias para que se comuniquen todos los equipos.

Puedes utilizar el Router para lograr el objetivo.

Una vez que todos se comuniquen, desde la PC9 ingresa a: www.redes.com

Para la entrega, realiza capturas de cada una de las instrucciones de **toda** la actividad y adjunta en un documento junto con el subneteo.

Envía a la plataforma 2 archivos:

- .pka de la actividad
- Documento en PDF

¡Mucho éxito!!!

Activar Windows

Ve a Configuración para activar Windows.

Time Elapsed: 01:54:55

Completion: 68%

Top ☐ Dock [Check Results](#)

[Back](#) [3/3](#) [Next](#)