ETS2 Instrument Cluster User guide

A stand-alone digital instrument cluster for Euro Truck Simulator 2, shown in its own window that you can place anywhere.

Version 1.0.0 for Windows 10 and 11



Screenshots in this guide were taken with demonstration values.

Contact: johnevansau320@gmail.com

1. What it is

The ETS2 Instrument Cluster is a digital dashboard for Euro Truck Simulator 2 in the style of a modern truck cluster: a speedometer with a needle, gear, rev strip, fuel and AdBlue gauges, consumption, range, cruise-control setting, arrival time, clocks, odometer and trip, plus warning lamps.

It is a separate program from the ETS2 GPS apps, so you can put the cluster on a second monitor, below the game, or beside the GPS window, wherever you like. It only **reads** information from the game (through the TruckSim GPS Telemetry Server) and never sends anything to the game.

What you need

- Windows 10 or 11 (64-bit). Nothing else to install: the program carries everything it needs.
- Euro Truck Simulator 2 with the **TruckSim GPS Telemetry Server** installed and running. This is the same source the ETS2 GPS apps use. The cluster asks it for the truck's data about ten times a second.
- The game should be run **windowed or borderless** if you want the cluster window to stay on top of it on the same monitor. On a second monitor any mode works.

> **TIP** The cluster does not need the ETS2 GPS app. They are independent: use either one, or both side by side.

2. Installing

2.1 With the setup program (recommended)

1. Download **Ets2ClusterSetup-1.0.0.exe** from the **Releases** page of the ETS2-Intrument-Cluster repository on GitHub.
2. Double-click the file. It installs for your user only, so **no administrator rights are needed**.
3. Choose whether to add a desktop shortcut, and whether the cluster should start automatically when you log in to Windows. Both are optional and off by default.
4. Tick *Start the instrument cluster now* on the last page, or start it later from the Start Menu: **ETS2 Instrument Cluster**.

The setup program also puts a shortcut to this guide in the Start Menu folder. To remove the program, use *Settings* > *Apps* > *Installed apps*; the uninstaller asks whether to delete your saved window position and settings too.

2.2 Without installing (portable)

Download **Ets2Cluster-portable-1.0.0.zip**, unpack it to any folder (for example on a USB stick) and run **Ets2Cluster.exe**. The settings are still kept in `%APPDATA%\ETS2-Cluster`.

> **NOTE** **Windows SmartScreen or your antivirus may warn about the setup program the first time.** The program is new and is not signed with a paid code-signing certificate, and some security programs are cautious about files they have not seen before. Check that the file you downloaded is the one published on the Releases page by comparing its SHA-256 checksum (the release page lists it; in PowerShell type `Get-FileHash .\Ets2ClusterSetup-1.0.0.exe`). If your security program still flags it, you can report it to the vendor as a false positive. Please do not switch your antivirus off.

3. First start

1. Start the **TruckSim GPS Telemetry Server** and then Euro Truck Simulator 2 (the order does not matter).
2. Start **ETS2 Instrument Cluster**. A window with the cluster opens in the middle of your main screen.
3. Load a profile and get into the truck. The needle, gauges and numbers come alive as soon as the game is running a drive.

Until the game is connected the cluster shows its layout dimmed with a message in the middle:

Message	Meaning
Waiting for the game	The telemetry server answers, but the game is not running or is not in a drive yet.
Telemetry server not reachable	The cluster cannot reach the telemetry server: it is not running, or it is on another address (see section 7).

4. Reading the cluster

The cluster is drawn on a 16:9 canvas and scales to any window size, so it looks the same large or small. The numbers in the picture match the list below.




The cluster with demonstration values. 1 lamps, 2 speed, 3 dial, 4 gear, 5 rev strip, 6 diesel, 7 AdBlue, 8 left panel, 9 right panel, 10 bottom row, 11 temperatures.

	What it shows
1	**Lamps**: the left and right **turn signals** (green when on) and the **low beam** (green) and **high beam** (blue) symbols. Dim symbols are off.
2	**Speed** in big digits, with the unit (km/h or mph). The digits turn **amber** when you are more than 3 km/h (2 mph) over the speed limit.
3	**Dial** with a red needle that glides between updates. The tick marks light up as far as your speed. A **green mark** shows the cruise-control setting and an **amber triangle** the current speed limit (red while you are over it).
4	**Gear**: for an automatic gearbox *A 12* means automatic in 12th; *N* is neutral and *R* reverse. A manual gearbox shows just the number.


	What it shows
5	**Rev strip**: engine speed in hundreds of rpm with a red marker (amber near the limiter).
6	**Diesel gauge** (green) with the level in per cent, *1/2* in the middle and *E* at the bottom. It turns red when the game raises its low-fuel warning.
7	**AdBlue gauge** (blue), the same way.
8	**Left panel**: *Average consumption* (the game's own figure), *This trip* (measured by the cluster since the last trip reset; shows -- until you have driven a short way) and *Range* (amber when fuel is low).
9	**Right panel**: the *Cruise control* setting (green when cruise control is on, -- when off), the *Arrival (ETA)* on the game clock for the route the game's navigation is following, and the *Speed limit*.
10	**Bottom row**: *Game time*, *Rest in* (time until the game says you need a rest; amber under 30 minutes), *Trip* distance and *Odometer*.
11	**Coolant** and **oil** temperature in the top corners (red when the game raises a warning). The outside temperature is not available from the game.

5. Warnings and states

The cluster changes its look to tell you what is going on without reading any numbers.



Over the speed limit: 98 km/h in a 90 zone. The speed digits and the glow beside the dial turn amber and the limit marker turns red.



Several status tags at once: engine brake, retarder step 2, wipers, beacon, and the air, fuel and AdBlue warnings. Low diesel and AdBlue show red.

Tag	Colour	Meaning
P BRAKE	red	The parking brake is on.
ENGINE BRAKE	amber	The engine brake is on.
RETARDER n	amber	The retarder is working at step n.
WIPERS	grey	The wipers are on.
BEACON	amber	The beacon (roof light) is on.
AIR	red	Low air pressure (warning or emergency).
OIL	red	Low oil pressure.
COOLANT	red	Coolant temperature warning.
BATTERY	red	Battery voltage warning.
FUEL	amber	Low fuel.
ADBLUE	amber	Low AdBlue.

6. Moving, sizing and the menu

Action	How
Move the cluster	Drag it anywhere with the mouse.
Resize	Drag the grip in the bottom right corner, or turn the mouse wheel over the cluster. The 16:9 shape is kept.
Opacity (see-through)	Hold **Ctrl** and turn the mouse wheel, or choose it in the menu.
Full screen	Double-click the cluster, or press **F11**. Double-click or **F11** or **Esc** to leave full screen.
Menu	Right-click the cluster.

The right-click menu


Item	What it does
Always on top	Keeps the cluster above other windows (on by default).
Opacity	100 % down to 40 %. A see-through cluster lets the game show through.
Size	Small (640 x 360), Medium (960 x 540), Large (1280 x 720), Extra large (1600 x 900) or Full screen.
Units	**km/h and km** or **mph and miles**. This changes the speed, the dial scale, the cruise and limit values, the range, the trip and the odometer.
Show the truck make	Shows or hides the make (VOLVO, SCANIA ...) under the speed.
Reset trip	Starts the trip distance and the trip consumption again from zero.
Telemetry server address...	The address of the TruckSim GPS Telemetry Server (usually 127.0.0.1:31377).
Reset window position and size	Puts the cluster back in the middle of the main screen at the medium size.
Close	Closes the cluster.

The position, size, opacity and options are remembered in `%APPDATA%\ETS2-Cluster\cluster.json` and used next time. If a monitor has been unplugged, the cluster starts on your main screen instead of off-screen.

> **TIP** The trip counter starts the first time the cluster sees your truck. Refuelling is ignored when working out the trip consumption.

7. Using it with the GPS and the game

Because the cluster is its own window, you decide where it goes. A common arrangement is the GPS and the cluster each on its own part of a second monitor, or the cluster along the bottom of the game window.



One possible arrangement: the game, the ETS2 GPS window and the cluster, each in its own place.

- Run the game **windowed or borderless** if the cluster should appear above it on the same monitor. A game in exclusive full screen hides every other window.
- Leave **Always on top** on so that the game does not cover the cluster. Use **Opacity** if you want to see the game through it.
- The cluster and the ETS2 GPS app do not need each other; they both read the same telemetry server.
- To start the cluster with Windows, tick *Start the instrument cluster when I log in* in the setup program.

Telemetry server address

The cluster uses `127.0.0.1:31377`, which is right when the telemetry server runs on the same PC as the cluster. To show the cluster on **another PC**, right-click the cluster, choose *Telemetry server address...* and enter that PC's address and port 31377 (for example 192.168.1.20:31377). That PC's firewall must allow the connection.

8. Troubleshooting

Problem	What to check
Telemetry server not reachable	Start the TruckSim GPS Telemetry Server. If it runs on another PC or port, right-click the cluster > *Telemetry server address...*.
Waiting for the game	The server is running but the game is not, or is not in a drive. Start Euro Truck Simulator 2 and load a profile.
All numbers stay at zero	The game may be paused or on the menu, or the telemetry plugin is not loaded (check the telemetry server's own page).
The cluster is hidden behind the game	Run the game windowed or borderless, and make sure *Always on top* is ticked in the menu.
The cruise mark is in the wrong place	The cluster treats the cruise setting as the same unit as the speed. Tell the author if you see a mismatch.
The trip distance is odd	Right-click > *Reset trip*. After a profile or truck change the counter keeps counting from the old reading until it is reset.
The window is off-screen or the wrong size	Right-click > *Reset window position and size*. If you cannot reach the menu, close the cluster and start it again: it comes up on the main screen.
The setup program or the app is flagged by an antivirus	See the note in section 2. Compare the SHA-256 checksum with the one on the Releases page and report a false positive to the vendor.

Command-line options (for testing)

Option	What it does
`--demo`	Shows made-up values instead of reading the game, to try the layout without the game. `--demo-state over` or `warn` picks other made-up states.
`--host 127.0.0.1:31377`	Uses this telemetry server address for this run.
`--config file.json`	Uses this settings file instead of the default one.
`--snapshot out.png`	Draws the cluster to a picture and quits.

Where to get it and help

- The program and this guide: github.com/johnevansau320/ETS2-Intrument-Cluster (Releases page).
- The TruckSim GPS Telemetry Server: github.com/TruckSim-GPS/trucksim-gps-server
- The ETS2 GPS apps (map and route guidance): github.com/johnevansau320/ETS2GPS and github.com/johnevansau320/ETS2GPS-Win
- **Contact** (questions, problems, ideas): johnevansau320@gmail.com
- ETS2 and Euro Truck Simulator 2 are trademarks of SCS Software. This project is not affiliated with or endorsed by SCS Software.