NZTopo50-BW15

Edition 1.04 Published 2026 Revised for selected changes in 2026.

A Map Reading Guide and more information about map updates and trig geodetic codes are available at www.linz.govt.nz

Toitū Te Whenua LINZ values your feedback:

We welcome advice of errors omissions or change suggestions: email topography@linz.govt.nz with "Topo50 Map Feedback" in your subject line, or phone 0800 665 463.




NZTopo50-BW15 Ōkārito

Used by Emergency Services in Aotearoa New Zealand

Ōkārito

NZTopo50-BW15 **1:50 000**



SCALE 1:50 000

THE VERTICAL INTERVAL BETWEEN THE CONTOURS IS 20 METRES

1 0 1 2 3 4 5 6 7 8 9 10 kilometers

MAGNETIC NORTH on this map is 24½° (436 mils) EAST of GRID NORTH during 2023 increasing at the rate of approx ½° (9 mils) over 6 years.

HORIZONTAL DATUM: New Zealand Geodetic Datum 2000 (NZGD2000)
For practical purposes, NZGD2000 equates to WGS84

VERTICAL DATUM: Mean Sea Level

PROJECTION: New Zealand Transverse Mercator 2000 (NZTM2000)

PARAMETERS

Spheroid: GRS80; Scale Factor: 0.9996
Origin Latitude: 0 South; Origin Longitude: 173 East
False Northing: 10 000 000mN; False Easting: 1 600 000mE

TO GIVE A GRID REFERENCE ON THIS MAP
(To the nearest 100 metres)

Sample Point: · *Mt Cavendish (1572107E 5173228N)*

East		North	
1. Locate the first VERTICAL grid line to the LEFT of the point		4. Locate the first HORIZONTAL grid line BELOW the point	
2. Read the grid values labelling the line in either the top or bottom margin or across the middle of the map	77	5. Read the grid values labelling the line in either the left or right margin of the map	73
3. Estimate the tenths of a grid square from the grid line to the point	1	6. Estimate the tenths of a grid square from the grid line to the point	7
Grid Reference (Quote sheet number first) :	771		737

BX24771737

CROWN COPYRIGHT RESERVED