

EC2

Dashboard
EC2 Global View
Events

Instances

Instances
Instance Types
Launch Templates

Instances (10) Info



Connect

Instance state

Actions

Launch instances

Find Instance by attribute or tag (case-sensitive)

All states

< 1 > Settings

☐	Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone
☐	ANSIBLE	i-0fd86c3eeac962116	Running	t2.micro	2/2 checks passed	View alarms	us-east-1c
☐	SLAVE-01	i-007f05f2977f349a7	Running	t2.micro	2/2 checks passed	View alarms	us-east-1c
☐	SLAVE-02	i-06035b80e664d8eb3	Running	t2.micro	2/2 checks passed	View alarms	us-east-1c
☐	SLAVE-03	i-0d89246a7b616b4f7	Running	t2.micro	2/2 checks passed	View alarms	us-east-1c

```
--  
- name: Install Apache Web Server on Amazon Linux  
  hosts: webservers  
  become: yes  
  tasks:  
    - name: Install Apache (httpd)  
      yum:  
        name: httpd  
        state: present  
  
    - name: Start and enable Apache service  
      service:  
        name: httpd  
        state: started  
        enabled: yes
```

```
- name: Create a new user with sudo
hosts: all
become: yes
tasks:
  - name: Create user with password
    ansible.builtin.user:
      name: surendra
      state: present
      groups: wheel
      append: yes
      shell: /bin/bash
      password: "{{ 'Suri@123' | password_hash('sha512') }}"
```

```
[root@ip-172-31-20-86 ~]# vim suri.yaml
[root@ip-172-31-20-86 ~]# ansible-playbook suri.yaml
```

```
PLAY [Install Apache Web Server on Amazon Linux] *****
```

```
TASK [Gathering Facts] *****
```

```
[WARNING]: Platform linux on host 172.31.28.95 is using the discovered Python interpreter at /usr/bin/python3.9, but future installation of another Python interpreter could change the meaning of that path. See https://docs.ansible.com/ansible-core/2.15/reference\_appendices/interpreter\_discovery.html for more information.
```

```
ok: [172.31.28.95]
```

```
[WARNING]: Platform linux on host 172.31.20.154 is using the discovered Python interpreter at /usr/bin/python3.9, but future installation of another Python interpreter could change the meaning of that path. See https://docs.ansible.com/ansible-core/2.15/reference\_appendices/interpreter\_discovery.html for more information.
```

```
ok: [172.31.20.154]
```

```
TASK [Install Apache (httpd)] *****
```

```
ok: [172.31.20.154]
```

```
ok: [172.31.28.95]
```

```
TASK [Start and enable Apache service] *****
```

```
ok: [172.31.20.154]
```

```
ok: [172.31.28.95]
```

```
PLAY [Create a new user with sudo] *****
```

```
TASK [Start and enable Apache service] *****
ok: [172.31.20.154]
ok: [172.31.28.95]

PLAY [Create a new user with sudo] *****

TASK [Gathering Facts] *****
ok: [172.31.28.95]
ok: [172.31.20.154]

TASK [Create user with password] *****
[DEPRECATION WARNING]: Encryption using the Python crypt module is deprecated. The Python crypt module is deprecated and will be removed from Python
3.13. Install the passlib library for continued encryption functionality. This feature will be removed in version 2.17. Deprecation warnings can be
disabled by setting deprecation_warnings=False in ansible.cfg.
[DEPRECATION WARNING]: Encryption using the Python crypt module is deprecated. The Python crypt module is deprecated and will be removed from Python
3.13. Install the passlib library for continued encryption functionality. This feature will be removed in version 2.17. Deprecation warnings can be
disabled by setting deprecation_warnings=False in ansible.cfg.
changed: [172.31.28.95]
changed: [172.31.20.154]

PLAY RECAP *****
172.31.20.154      : ok=5    changed=1    unreachable=0    failed=0    skipped=0    rescued=0    ignored=0
172.31.28.95      : ok=5    changed=1    unreachable=0    failed=0    skipped=0    rescued=0    ignored=0
```