Intersections

MCrafterzz edited this page on Sep 13, 2019 · 38 revisions

Intersections

Intersections are generated automaticly when connecting two roads end/start points together. For roundabout documentation see this.

`[Base Material]` The base material used. Use one of the included materials or create your own. Default is controlled by Settings.

`[Overlay Material]` Renders above the other material. Default is controlled by Settings.

`[Physics Material]` The physics material used.

`[Y Offset]` Increase this value to make the intersection generate heigher up. This can be used to hide uneven terrain under the intersection. It will create a gap under tho. 0,02 is the default value.

`[Stretch Texture]` Should the texture be stretched or repeated? Is false by default which gives the best result for the asphalt intersection. Enable this when for example using the grid intersection texture.

`[Texture Scale]` Has a default value of 1. The x-scale of the texture, change this so that it fits the thickness of the roads' lines.

`[Resolution Multiplier]` Default value is 1. Multiplies with the global resolution, so use this if you want this specific road to be more or less detailed than the rest.

`[Reset Curve Points On Update]` True is the default value. Determines if the curve positions should be placed automatically or manually.

Main Roads



The following options are configured per main road:

`[Start Index]` The index of the road connection where the main road should start. 0 is the default value.

`[End Index]` The index of the road connection where the main road should end. Default is 1.

`[Material]` Default is controlled by Settings. Determines what material the main road should use.

`[Flip Texture]` Default value is false. If true then the main road material will be flipped.

`[Remove Main Road]` Removes the main road.

Bridge

`[Generate Bridge]` Is false by default. If true it will generate a bridge that looks like this:



These options are only showed if generate bridge is true:

`[Bridge Materials]` This is a list of materials used for the bridge. The materials overlay eachover. Defaults are controlled by Settings.

`[Y Offset First Step]` Determines how far down the first "step" should be. Default is 0.25.

`[Y Offset Second Step]` Determines how far down the second "step" should be. Default is 0.5.

`[Width Percentage First Step]` Determines how wide the first "step" should be relative to the roads width (extra meshes included). Default is 0.6.

`[Width Percentage Second Step]` Determines how wide the second "step" should be relative to the first step. Default is 0.6.

`[Extra Width]` How much wider should the bridge base be than the road? Default is 0.2

Pillar Placement

This option is only showed if generate bridge is true:

`[Place Pillar]` Should a pillar be placed? Default is true

These options are only showed if place pillar is true:

`[Prefab]` The pillar prefab. Default is controlled by Settings.

`[Extra Height]` How much highter should the pillar be than the distance between the bottom of the bridge mesh and the ground? Default is 0.2.

`[XZ Scale]` The X/Z scale of the pillar. 1 is default.

Extra Meshes

`[Outer Extra Meshes Controlled By Roads]` Defaults to false. When true, the outer extra meshes are automatically created every time you generate the roundabout, to match the connected roads. You will not be able to edit those extra meshes or add new ones. This option was added so that you don't have to manually create a lot of extra meshes and modify them to fit the connected roads.

These options are configured per extra mesh:

`[Index]` Determines where the extra mesh should generate. The default value of 0 will generate it between the first and second connections.

`[Base Material]` The base material of the extra mesh. Default is controlled by Settings.

`[Overlay Material]` The overlay material of the extra mesh. Default is controlled by Settings.

`[Physic Material]` The extra mesh's physic material. Is none by default.

`[Start Width]` The start width of the extra mesh. All points will loop between these values depending on how near they are to the end point. Defaults to 1.

`[End Width]` The end width of the extra mesh. Default value is 1.

`[Flipped]` Defaults to false. Should the extra mesh's uvs be flipped? Setting this to true will make the texture's right side be on the outer edge.

`[Y Offset]` How far up should the extra mesh generate? This is added to the roads y offset so that moving the roads keeps the right proportion. 0 is default.

`[Duplicate Extra Mesh]` Duplicates the extra mesh. Useful when you for example want the same mesh on all connections.

`[Remove Extra Mesh]` Removes the extra mesh.

Buttons

`[Add Main Road]` Adds a main raid to the intersection.

`[Add Extra Mesh]` Adds another extra mesh to the intersection.

`[Reset Curve Points]` Resets the position of the intersection's curve points.

`[Generate Intersection]` Regenerates the intersection mesh. This is done automaticly so this shouldn't be used much.

Pages 12

Tutorials:

- Getting Started/Controls
- Using The Creation Gui
- Using The Tool in SRP

Customization:

- Roads
- Road Segments
- Prefab Lines
- Intersections
- Roundabouts
- Road Systems
- Traffic Lights
- Settings

Report A Bug/Post A Suggestion

Clone this wiki locally

`https://github.com/MCrafterzz/ro`