Prefab Lines

MCrafterzz edited this page on Jul 6, 2019 · 27 revisions

Prefab Lines

Depending on what options you select all options won't be showed.

`[Rotate Alongst Curve]` Should the prefab rotate so they follow the curve or should they always point towards the same direction. Is true by default.

`[Rotation Direction]` Determines which direction the prefabs are pointing when placed. Available options are Left, Right, Forward and Backward. Left is the default and the only one that's allowed when the bend object option is selected.

`[Y Rotation Randomization]` Is only showed when fill gap is 0. Adds a randomization to prefabs rotation. Setting this to 50 for example will make the prefabs rotate between -25 and +25 degrees relative to their original position. Default is 0 which is no random rotation.

`[Bend Prefabs]` Should the prefabs be bent alongst the curve. If true the objects will follow the curve more precisely. Cannot be used if rotate alongst curve is false. It's true by default.

`[Fill Gap]` Should the gap between the prefabs be filled in. This will make the prefab line look like one smoothly connected mesh. Cannot be used if rotate alongst curve is false. Is true by default.

`[Spacing]` Determines how part apart the prefabs should be placed. This is automaticly calculated when choosing which prefab to place.

`[Calculate Spacing (X)]` Automaticly calculates spacing depending on the objects x-size.

`[Calculate Spacing (Z)]` Automaticly calculates spacing depending on the objects z-size.

`[Vertex Y Modification]` Can be none, match terrain or match curve. None meens that the vertices y-positions aren't modified at all. Match terrain modifies the y-position so that it follows the terrain that's under. Match curve makes the height match the curve. Is none by default.

`[Check Terrain Height]` Only shows when vertex y modification is match terrain. Determines how high up terrain should be detected. 0 meens that terrain will be checked for from the bottom of the prefab and downwards which meens that the terrain won't be detected if the prefab is in it. A higher value has the disadvantage of detecting other objects above the mesh. Increase it when you prefab line is on a steep slope. Default value is 1.

`[Point Calculation Divisions]` A higher value will place the prefabs with more accurate spacing, at the cost of performance. 100 is the default value and it's not recommended to go below that.

Prefabs

`[Prefab]` Determined which prefab is placed. A few are included but any prefab can be used as long as it has a mesh filter. Default is controlled by Settings.

`[Start Prefab]` Is used to have a different first prefab than the rest of the prefab line. Useful for guardrails and similar that attach to the ground. Default is controlled by Settings.

`[End Prefab]` Is used to have a different ending prefab than the rest of the prefab line. Default is controlled by Settings.

Scaling

`[Prefab X Scale]` The x scale of the prefab. 1 is the default value.

`[Prefab Y Scale]` The y scale of the prefab. Defaults to 1.

`[Prefab Z Scale]` The z scale of the prefab. 1 the default.

Buttons

`[Flip Prefab Line]` Flips the prefab line, so what previously was the start is now the end. Use this if you want to continue adding points from the start of the prefab line. Note that it won't work if your last point is an control point.

`[Reset Prefab Line]` Removes all points

`[Place Prefabs]` Places the prefabs again. This is done automaticly so this shouldn't be used much.

Pages 12

Tutorials:

- Getting Started/Controls
- Using The Creation Gui
- Using The Tool in SRP

Customization:

- Roads
- Road Segments
- Prefab Lines
- Intersections
- Roundabouts
- Road Systems
- Traffic Lights
- Settings

Report A Bug/Post A Suggestion

Clone this wiki locally

https://github.com/MCrafterzz/ro