Roads

MCrafterzz edited this page on Jul 30, 2019 · 31 revisions

Roads

Roads are the whole base of this extension but most variables are changed per segment. There are still some options tho.

`[Y Offset]` Changing this renders the mesh higher or lower. Useful for rendering above terrain instead of texture fighting with it. The default value is 0,02 and is so small that it isn't noticed.

`[Segment Preset]` This is the preset that is applied to the first segment when created. The other segments when created will copy all thier options from the last one. Two sidewalk- and three linepresets are included but you can easly create your own. Customize a road segment and then change that as a new preset. This is explained on the unity wiki.

`[Segment To Copy]` If segment preset is null then this the first segment's values will be copied from this segment. Default value is null.

`[Resolution Multiplier]` Default value is 1. Multiplies with the global resolution, so use this if you want this specific road to be more or less detailed than the rest.

`[Create Intersections]` Should this road create intersections? Disable this when using roads to create lines and other details. Default value is true.

`[Generate Collider]` True is the default value. Determines if the road should have a collider or not.

Start Lane Markings

These following variables are only shown if the road's first start point is connected to an intersection or roundabout:

`[Lanes]` How many lanes does the road have? Set this to 0 to disable this feature. Default value is 2.

The following options are only showed if lanes is more than 0:

`[Scale]` The scale of the lane markings, 1 is the default value.

`[Repeations]` Determines how many rows of lane markings there should be. Has a default value of 1.

`[Start Intersection Offset]` The distance between the intersection connection and the first row of lane markings. Defaults to 0.7 but changes depending on scale.

This following option is only available if repeations is set to more than 1:

`[Continuous Offset]` Determines the distance between each row of turn markings.

`[Y Offset]` Should the object be on the ground or raised up a little bit? Increase this if you can't see the whole object or it's z-fighting. The default value of 0 should be fine in most cases.

These following options are only shown if lanes is more than 0. The next 3 variables are shown per lane marking so their will be as many options as lanes. Depending on these three options different lane marking prefabs will be chosen.

`[Left]` Defaults to false. Determines if the marker should have an arrow turning to the left.

`[Forward]` True is the default value. Should the lane marker have an arrow pointing forwards?

`[Right]` Default is false. Should it have an arrow pointing to the right?

`[Reset Lane Markers]` Resets the above variables.

End Lane Markings

These following variables are only shown if the road's last end point is connected to an intersection or roundabout:

`[Lanes]` How many lanes does the road have? Set this to 0 to disable this feature. Default value is 2.

The following options are only showed if lanes is more than 0:

`[Scale]` The scale of the lane markings, 1 is the default value.

`[Repeations]` Determines how many rows of lane markings there should be. Has a default value of 1.

`[Start Intersection Offset]` The distance between the intersection connection and the first row of lane markings. Defaults to 0.7 but changes depending on scale.

This following option is only available if repeations is set to more than 1:

`[Continuous Offset]` Determines the distance between each row of turn markings.

`[Y Offset]` Should the object be on the ground or raised up a little bit? Increase this if you can't see the whole object or it's z-fighting. The default value of 0 should be fine in most cases.

These following options are only shown if lanes is more than 0. The next 3 variables are shown per lane marking so their will be as many options as lanes. Depending on these three options different lane marking prefabs will be chosen.

`[Left]` Defaults to false. Determines if the marker should have an arrow turning to the left.

`[Forward]` True is the default value. Should the lane marker have an arrow pointing forwards?

`[Right]` Default is false. Should it have an arrow pointing to the right?

`[Reset Lane Markers]` Resets the above variables.

Buttons

`[Flip Road]` Flips the road, so what previously was the start is now the end. Use this if you want to continue adding points from the start of the road. Note that it won't work if your last point is an control point.

`[Reset Road]` Removes all the roads segments and points.

`[Generate Road]` Regenerates the road mesh. This is done automaticly so this should rarely be useful.

Pages 12

Tutorials:

- Getting Started/Controls
- Using The Creation Gui
- Using The Tool in SRP

Customization:

- Roads
- Road Segments
- Prefab Lines
- Intersections
- Roundabouts
- Road Systems
- Traffic Lights
- Settings

Report A Bug/Post A Suggestion

Clone this wiki locally

https://github.com/MCrafterzz/ro