Settings

MCrafterzz edited this page on Sep 13, 2019 · 14 revisions

Settings

The settings that all road-related objects use. You can find it in "Project Settings > Road Creator"

`[Point Size]` The size of the displayed points for roads, intersections and prefab lines. This is 0,5 by default.

`[Resolution]` This affects the amount of vertices roads will generated. Higher value will result in smoother curves but much higher performance cost when generating a road. Default value is 0,25 which gives a low poly look.

`[Hide non-editable Children]` Is true by default which means that non-editable objects such as prefab lines placed prefabs and road segments meshes are hidden. As they arn't editable they just clutter the hierarchy. Disable this if you want to see all objects. Worth noting is that hiding objects is done on creation so modifying this value won't change existing road segments for example.

Road Guidelines

`[Road Guidelines Length]` How long should the road guidelines be? Default is 5.

`[Road Guidelines Display Distance]` Determines how close the mouse has to be for the guideline to be shown. Default value is 10.

`[Road Guidelines Snap Distance]` How far away does the mouse have to be to snap to guidelines? Defaults to 1.

Defaults

`[Default Lanes]` The default amount of lanes that a road has. Is used by lane markings so set it to 0 to have them disabled by default. Default value is 2.

`[Default Base Material]` The default base material used by road segments, extra meshes and intersections. Is Asphalt by default.

`[Default Road Overlay Material]` Default road overlay material, defaults to 2L Road.

`[Default Extra Mesh Overlay Material]` The overlay material that extra meshes use by default. Default material is null.

`[Default Intersection Overlay Material]` Default intersection overlay material, default is Asphalt Intersection.

`[Default Intersection Main Road Material]` Defaults to 2L 2 Sides Main Road. The default material that intersections use for main roads.

`[Default Roundabout Connection Sections Material]` Renders above the connection parts of the roundabout, this is what makes the center line go round the whole roundabout and not just between connections. Defaults to 2L Roundabout.

`[Default Simple Bridge Materials]` A array of materials used by road segments simple bridge mesh. Is Concrete by default.

`[Default Pillar Prefab]` Default pillar prefab used by both road segments and intersections. Is Oval Bridge Pillar by default.

`[Default Custom Bridge Prefab]` Determines what mesh to use by default when road segments generate custom bridge is true. Is Suspension Bridge by default.

`[Default Prefab Line Prefab]` What prefab should prefab lines use by default? Defaults to Concrete Barrier.

`[Reset Default Values]` Resets all the default variables to their default values.

Turn Markings

All turn marking variables default to their corresponding turn marking prefab.

`[Left Turn Marking]` The left turn marking prefab.

`[Forward Turn Marking]` The forward turn marking prefab.

`[Right Turn Marking]` The right turn marking prefab.

`[Left And Forward Turn Marking]` The left and forward turn marking prefab.

`[Right And Forward Turn Marking]` The right and forward turn marking prefab.

`[Left And Right Turn Marking]` The left and right turn marking prefab.

`[Left, Right And Forward Turn Marking]` The left, right and forward turn marking prefab.

`[Reset Turn Markings]` Resets the turn markings to their default prefabs.

Colours

`[Point Colour]` The colour of roads and prefab lines main points. Default is red.

`[Control Point Colour]` The colour of roads and prefab lines control points. Yellow is default.

`[Intersection Point Colour]` Intersections curve point colour. Green is default.

`[Cursor Colour]` The colour of the cursor. Is blue by default.

`[Road Guidelines Colour]` The colour of roads main guidelines. Default is a light green.

`[Road Control Guidelines Colour]` The colour of roads control point guidelines. Default is a dark green.

`[Reset Colours]` Changes colours back to default.

Pages 12

Tutorials:

- Getting Started/Controls
- Using The Creation Gui
- Using The Tool in SRP

Customization:

- Roads
- Road Segments
- Prefab Lines
- Intersections
- Roundabouts
- Road Systems
- Traffic Lights
- Settings

Report A Bug/Post A Suggestion

Clone this wiki locally

https://github.com/MCrafterzz/ro