

1. Open the official RustDesk website

On the computer that needs support, open **rustdesk.com**. Click **Download** at the top right.
This guide is for Windows. Already installed RustDesk? Start **Part 2 on page 5**.



2. Download and open the Windows file


On the GitHub release page, find the **Windows** column. For most PCs, click **EXE** in the **x86-64 (64-bit)** row.
When the download finishes, press **Ctrl + J** in your browser and open **rustdesk-...-x86_64.exe**.
A Windows ARM PC needs the EXE in the **AArch64 (ARM64)** row instead.



Actual official GitHub release page. The file in these screenshots is RustDesk 1.5.0 for 64-bit Windows.

3. Install RustDesk


If the main RustDesk screen opens first, click **Install** near the bottom left to reach this screen.
Keep the default installation path and shortcuts. Click **Accept and install**.
If Windows asks to allow RustDesk to make changes, click **Yes**. If it needs an admin password, ask your administrator.



Actual RustDesk installation screen. The RustDesk Printer component is optional for remote support.

4. Finish installation and open RustDesk

Wait for installation to finish. Open **RustDesk** from the desktop or Start menu if it does not open automatically.
You should see **Your Desktop** and your **ID**. At the bottom, check for the green dot and **Ready**.
Installation is complete. Continue with **Part 2 on page 5** to set up the password.




BOTTOM OF THE RUSTDESK WINDOW



Actual installed app, with private IDs, passwords and connection history hidden. Main screen and status bar shown.

1. Open Settings

Open RustDesk on the computer that needs support.
Under **Your Desktop**, click the **three dots next to ID**. The **Settings** tab opens.




You are setting up access **to this computer**. You do not need to enter anything in **Control Remote Desktop**.

Actual RustDesk main screen, enlarged upper section. Private values are hidden.

2. Open Security and unlock the controls


1. Click **Security** on the left. **2.** Click **Unlock security settings** at the top, if shown.
Confirm the Windows permission request for RustDesk. Ask your administrator if Windows requires an admin password.
The settings become available. Scroll down on the right to **Password**.



Actual Security screen before unlocking. Gray controls become available after administrator approval.

3. Allow both password types

In the **Password** section: **1.** Select **Accept sessions via password** in the dropdown.
Accept sessions via both also allows password access. **2.** Select the radio button **Use both passwords**.
This allows both the one-time password and the permanent password you will set next.




The screenshot shows the controls while locked. If yours are gray, complete **Unlock security settings** on page 6 first.

Actual Password section, enlarged for readability. Use both passwords is selected in this screenshot.

4. Set your permanent password

Click **Set permanent password**. Then complete the password window as described below.
Keep **Use both passwords** selected.



IN THE SET PASSWORD WINDOW

1 Password

Enter a new password for RustDesk. Use at least 12 characters, with uppercase and lowercase letters and a number.

2 Confirmation

Type exactly the same password again.

3 OK


Click OK to save. The window closes when the password is accepted.

Keep this password so you can give it to Postiqo Support when requested. Use a password made specifically for RustDesk.

Actual Set permanent password button. The password-entry window is described in text and is not shown.

5. Send your ID and permanent password

Return to **Home**. When **Postiqo Support asks**, send these two items in your existing private support conversation:
1. The number under **ID** in Your Desktop. **2.** The **permanent password you created on page 8**.



MESSAGE TO POSTIQO SUPPORT

RustDesk ID: [your ID]

Permanent password: [the password you set]


The one-time password on the main screen is a separate password. Send the permanent password you created for ongoing support access.

This lets support reconnect without you clicking Accept each time. Share these details only with the support team you are working with.

Actual Your Desktop panel. Private values are hidden; the message on the right is a template, not real access details.

6. Keep the computer ready for support

Open **Settings > General** and find **Service**.
If the button says **Stop**, the service is already running. Leave it running.
If the button says **Start**, click it to start the service.



READY CHECK

1. RustDesk shows **Ready**.

2. **Use both passwords** is selected and your permanent password is saved.

3. Your computer stays **on, online and awake** while support needs access.

Cannot connect? Check the ID and password, the service, and the Ready status. Tell support the exact message you see.
Ending ongoing access later: change your RustDesk permanent password.

Official references: Windows installation | Unattended access setup | Latest official downloads

Postiqo Support guide for Windows. Verified with RustDesk 1.5.0 on October 28, 2026. Screens may vary slightly in other versions.

Actual General settings. A Stop button confirms that the RustDesk service is running.