





Assign ip address in all cisco routers



```
R1#
R1#
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int eth 0/0
R1(config-if)#ip add 50.0.0.1 255.0.0.0
R1(config-if)#no shut
R1(config-if)#exit
R1(config)#exit
R1#
*Sep 14 17:45:50.012: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int eth 0/1
R1(config-if)#ip add 172.16.0.1 255.255.0.0
R1(config-if)#no shut
R1(config-if)#exit
R1(config)#exit
R1#
*Sep 14 17:45:44.771: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

```
R1#
R1#
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int eth 0/1
R1(config-if)#ip add 172.16.0.1 255.255.0.0
R1(config-if)#no shut
R1(config-if)#exit
R1(config)#exit
R1#
*Sep 14 17:45:44.771: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

```
R1#show ip int brief
Interface      IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0    50.0.0.1        YES manual up          up
Ethernet0/1    172.16.0.1      YES manual up          up
Ethernet0/2    unassigned      YES TFTP down        down
Ethernet0/3    unassigned      YES TFTP down        down
R1#
```

```

R2#
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip add 192.168.2.1 255.255.0.0
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#exit
R2#
*Sep 14 17:47:57.415: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/1
R2(config-if)#ip add 172
*Sep 14 17:48:15.352: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config-if)#ip add 172.16.0.2 255.255.0.0
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#exit
R2#
*Sep 14 17:48:39.339: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#show ip int brief
^
% Invalid input detected at '^' marker.

R2(config)#exit
R2#show i
*Sep 14 17:48:56.300: %SYS-5-CONFIG_I: Configured from console by console
R2#show ip int brief
Interface                IP-Address      OK? Method Status      Prot
Ethernet0/0              192.168.2.1     YES manual up          up
Ethernet0/1              172.16.0.2      YES manual up          up
Ethernet0/2              unassigned      YES TFTP  down        down
Ethernet0/3              unassigned      YES TFTP  down        down

```

Enable dhcp server for HR department in R1

```

R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8

```

```

R1(config)#ip dhcp pool HR
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#exit
R1#
*Sep 14 17:58:13.971: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#

```

```
VPC-1

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.0.2/8 GW 50.0.0.1

VPC-1> 
```

```
VPC-2

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.3/8 GW 50.0.0.1

VPC-2> 
```

```
R1

*Sep 14 17:58:13.971: %SYS-5-CONFIG_I: Configured from console by console
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#show ip dhcp binding
      ^
% Invalid input detected at '^' marker.

R1(config)#exit
R1#
R1#
R1#
R1#
R1#
*Sep 14 18:01:55.177: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#
R1#
R1#show ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration        Type
                  Hardware address/
                  User name
50.0.0.2         0100.5079.6668.65    Sep 16 2026 01:33 AM    Automatic
R1# 
```

Add static route in R1 & R2

Enable dhcp server for SALES department in same R1

```
R1
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#ip route 192.168.2.0 255.255.255.0 172.16.0.2
R1(config)#
R1(config)#ip dhcp pool sales
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#
R1(dhcp-config)#
R1(dhcp-config)#default-route 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#exit
R1#
*Sep 14 18:07:58.957: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

Enable dhcp relay agent on router 2 client connected interface

```
R2
R2#
R2#
R2#
R2#
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int eth 0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#
R2(config-if)#
```

