


1. Ubuntu has UFW called Uncomplicated Firewall which can assign to manage the firewall. You can check the status as shown below.




2. You can allow an IP address using the “allow from” command.



3. You can also block using the “deny from” command.



4. If you restart your ssh server and try loggin in on the other side, it’ll work.



5. If you deny from the IP address, you won't be able to log in using ssh anymore.

```
rrc@rrc-ubuntu:~$ sudo ufw deny from 172.18.1.101
Rule updated
rrc@rrc-ubuntu:~$ sudo ufw status
Status: active

To                         Action      From
--                         ------      ----
Anywhere                   DENY        172.18.1.101
Anywhere                   DENY        172.18.0.0/16
```

6. You can also specify the destination you want to allow the user to visit.

```
rrc@rrc-ubuntu:~$ sudo ufw allow ssh
Rule added
Rule added (v6)
rrc@rrc-ubuntu:~$ sudo ufw status
Status: active

To                         Action      From
--                         ------      ----
Anywhere                   ALLOW       172.18.1.101
Anywhere                   DENY        172.18.0.0/16
22/tcp                     ALLOW       Anywhere
22/tcp (v6)                ALLOW       Anywhere (v6)
```

7. You can get more information on your status by typing verbose at the end.

```
rrc@rrc-ubuntu:~$ sudo ufw status verbose
Status: active
Logging: on (low)
Default: deny (incoming), allow (outgoing), disabled (routed)
New profiles: skip

To                         Action      From
--                         ------      ----
Anywhere                   ALLOW IN    172.18.1.101
Anywhere                   DENY IN     172.18.0.0/16
22/tcp                     ALLOW IN    Anywhere
22/tcp (v6)                ALLOW IN    Anywhere (v6)
```

8. You can also number your rules and see by typing numbered at the end.

```
rrc@rrc-ubuntu:~$ sudo ufw status numbered
Status: active

     To                         Action      From
     --                         ------      ----
[ 1] Anywhere                   ALLOW IN    172.18.1.101
[ 2] Anywhere                   DENY IN     172.18.0.0/16
[ 3] 22/tcp                     ALLOW IN    Anywhere
[ 4] 22/tcp (v6)                ALLOW IN    Anywhere (v6)
```

9. You can delete using numbers.

```
rrc@rrc-ubuntu:~$ sudo ufw delete 3
Deleting:
 allow 22/tcp
Proceed with operation (y|n)? y
Rule deleted
rrc@rrc-ubuntu:~$ sudo ufw status numbered
Status: active

     To                         Action      From
     --                         ------      ----
[ 1] Anywhere                   ALLOW IN    172.18.1.101
[ 2] Anywhere                   DENY IN     172.18.0.0/16
[ 3] 22/tcp (v6)                ALLOW IN    Anywhere (v6)
```

10. The other computer can still ping your device even if you block all traffic on the entire network.

```
rrc@rrc-ubuntu:~$ sudo ufw status numbered
Status: active

     To                         Action      From
     --                         ------      ----
[ 1] Anywhere                   DENY IN     172.18.0.0/16
```

```
jrice@kali-rrc:~$ ssh rrc@172.18.1.1
rrc@172.18.1.1's password:

jrice@kali-rrc:~$ ssh rrc@172.18.1.1
^C
jrice@kali-rrc:~$ ping 172.18.1.1
PING 172.18.1.1 (172.18.1.1) 56(84) bytes of data.
64 bytes from 172.18.1.1: icmp_seq=1 ttl=64 time=0.529 ms
64 bytes from 172.18.1.1: icmp_seq=2 ttl=64 time=0.488 ms
64 bytes from 172.18.1.1: icmp_seq=3 ttl=64 time=0.309 ms
64 bytes from 172.18.1.1: icmp_seq=4 ttl=64 time=0.511 ms
```

11. There is a file in “/etc/ufw” called “before.rules” which run first before our commands. You can block the ping by editing this file. And restart your service.

```
# ok icmp codes for INPUT
-A ufw-before-input -p icmp --icmp-type destination-unreachable -j DROP
-A ufw-before-input -p icmp --icmp-type time-exceeded -j DROP
-A ufw-before-input -p icmp --icmp-type parameter-problem -j DROP
-A ufw-before-input -p icmp --icmp-type echo-request -j DROP
```

```
rrc@rrc-ubuntu:/etc/ufw$ sudo ufw reload
Firewall reloaded
```

12. You can reset your firewall using the “ufw reset” command.

```
rrc@rrc-ubuntu:/etc/ufw$ sudo ufw reset
Resetting all rules to installed defaults. Proceed with operation (y|n)? y
Backing up 'user.rules' to '/etc/ufw/user.rules.20240423_121050'
Backing up 'before.rules' to '/etc/ufw/before.rules.20240423_121050'
Backing up 'after.rules' to '/etc/ufw/after.rules.20240423_121050'
Backing up 'user6.rules' to '/etc/ufw/user6.rules.20240423_121050'
Backing up 'before6.rules' to '/etc/ufw/before6.rules.20240423_121050'
Backing up 'after6.rules' to '/etc/ufw/after6.rules.20240423_121050'

rrc@rrc-ubuntu:/etc/ufw$ sudo ufw status
Status: inactive
```