1. Let's give our CentOS internet access. Set your eth1 to dynamic and restart your network.

```
PROXY_METHOD=none
BROWSER_ONLY=no
BOOTPROTO=dhcp
DEFROUTE=yes
IPV4_FAILURE_FATAL=no
IPV6INIT=yes
IPV6_AUTOCONF=yes
IPV6_DEFROUTE=yes
IPV6_FAILURE_FATAL=no
IPV6_ADDR_GEN_MODE=stable-privacy
NAME=eth1
UUID=23eb7fce-dd0b-4b7b-a37d-383be9c90712
DEVICE=eth1
ONBOOT=yes
```

2. Now, you can ping google which proves that you now have internet access. You can use the "df -h" command to check how much space you have.

```
[root@localhost network-scripts]# df -h /
Filesystem              Size  Used Avail Use% Mounted on
/dev/mapper/centos-root  6.2G  1.7G  4.5G  28% /
[root@localhost network-scripts]# _
```

3. Since we have both internet access and space, we are now going to see what updates are available on the internet. You can use the "yum" command.

```
[root@localhost network-scripts]# df -h /
Filesystem              Size  Used Avail Use% Mounted on
/dev/mapper/centos-root  6.2G  1.7G  4.5G  28% /
[root@localhost network-scripts]# _
```

4. Now, let's install GUI in CentOS

```
[root@localhost network-scripts]# yum groups install "GNOME Desktop" -y_
```

5. Reboot the computer using "reboot 0" and type the command "startx" to launch the GUI. If you want your CentOS computer to have GUI next time you restart, run the command shown below.

```
[root@localhost ~]# sudo systemctl set-default graphical.target
Removed symlink /etc/systemd/system/default.target.
Created symlink from /etc/systemd/system/default.target to /usr/lib/systemd/syst
em/graphical.target.
[root@localhost ~]#
```

6. If you don't want GUI, you can type "multi-user.target" instead of "graphical.target"

```
[root@localhost ~]# sudo systemctl set-default multi-user.target
Removed symlink /etc/systemd/system/default.target.
Created symlink from /etc/systemd/system/default.target to /usr/lib/systemd/syst
em/multi-user.target.
[root@localhost ~]#
```

7. We are now doing the same thing on Kali. Let's set the eth1 to dynamic.

```
source /etc/network/interfaces.d/*

# The loopback network interface
auto lo
iface lo inet loopback

auto eth0
iface eth0 inet static
        address 172.18.1.101
        netmask 255.255.0.0

auto eth1
iface eth1 inet dhcp
```

8. Restart your network and now, you'll have internet access. You can check your update using "apt update" command.

```
File  Actions  Edit  View  Help

kmin@kali-rrc:~$ sudo apt update
Get:1 http://kali.download/kali kali-rolling InRelease [41.5 kB]
Get:2 http://kali.download/kali kali-rolling/main amd64 Packages [19.2 MB]
Get:3 http://kali.download/kali kali-rolling/non-free amd64 Packages [194 kB]
Get:4 http://kali.download/kali kali-rolling/contrib amd64 Packages [114 kB]
Fetched 19.5 MB in 22s (908 kB/s)
Reading package lists ... Done
Building dependency tree
Reading state information ... Done
1132 packages can be upgraded. Run 'apt list --upgradable' to see them.
kmin@kali-rrc:~$
```

9. You can do the upgrade using the command shown below since the update command will only show you the list.

```
kmin@kali-rrc:~$ sudo apt dist-upgrade
```

10. You can install the latest ufw using the "install" command.

```
jrice@kali-rrc:~$ sudo apt install ufw
Reading package lists ... Done
Building dependency tree ... 50%
```