```
.386
   .model flat, stdcall
  option casemap :none
include \masm32\include\windows.inc
  include \masm32\include\user32.inc
  include \masm32\include\kernel32.inc
  includelib \masm32\lib\user32.lib
  includelib \masm32\lib\kernel32.lib
;#### User Library includes
         InputBox.lib
includelib
;#### // User Library includes
;#### Prototypes includes
include Prototypes.inc
;#### // Prototypes includes
  .data
                        db "MASM32 Prog 2", 0
         MsgBoxCaption
                        db "Ввод значений", 0
         InputCaption
                        db "Пожалуйста, введите значение",0
         InputBoxText
         ValueInputError
                        db "Вы не ввели значения", 13, 10
                        db "Повторить ввод?",0
         InputValue
                        db 100 dup (0)
         InputValueLength
                        db 100 dup (0)
```

db "Количество символов в введённой строке: %lu",0

MessageTemplate

```
.code
start:
     ; Вызов InputBox
     ;invoke InputBox, ADDR InputBoxText, ADDR InputCaption, ADDR InputValue
     push offset InputValue
     push offset InputCaption
     push offset InputBoxText
          InputBox
     call
     ; Проверка отклика от InputBox
     test EAX, EAX
           InputError
     jΖ
     invoke wsprintf, addr InputValueLength, addr MessageTemplate, EAX
     push 0 + MB ICONINFORMATION
                                       ; Параметр набора кнопок
     push offset MsqBoxCaption
                                       ; Параметр "адрес заголовка"
     push offset InputValueLength
                                       ; Параметр "адрес текста сообщения"
     push 0
                                       ; Параметр "родительское окно" - NULL
                                       ; Вызов АРІ-функции вывода сообщения на экран
           MessageBox
     call
     ; Кнопки для MessageBox
     ; 0 - OK
     ; 1 - OK & Cancel
     ; 2 - Abort, Retry & Ignore
     ; 3 - Yes, No & Cancel
     ; 4 - Yes & No
     ; 5 - Retry & Cancel
     ; 6 - Cancel, Repeat & Continue
```

```
: Шпоргалка с MSDN.COM
      ; Наборы кнопок
      ; MB ABORTRETRYIGNORE
                                     - 0x00000002L - The message box contains three push buttons: Abort, Retry, and Ignore
                                     - 0x00000006L - The message box contains three push buttons: Cancel, Try Again, Continue, Use
      : MB CANCELTRYCONTINUE
this message box type instead of MB ABORTRETRYIGNORE.
                                     - 0x00004000L - Adds a Help button to the message box. When the user clicks the Help button or
      ; MB HELP
presses F1, the system sends a WM HELP message to the owner.
                                     - 0x0000000L - The message box contains one push button: OK. This is the default.
      ; MB OK
      ; MB OKCANCEL
                                     - 0x00000001L - The message box contains two push buttons: OK and Cancel.
                                     - 0x00000005L - The message box contains two push buttons: Retry and Cancel.
      ; MB RETRYCANCEL
                                     - 0x00000004L - The message box contains two push buttons: Yes and No.
      ; MB YESNO
                                     - 0x00000003L - The message box contains three push buttons: Yes, No, and Cancel.
      ; MB YESNOCANCEL
      : Наборы иконок
                                      - 0x00000030L - An exclamation-point icon appears in the message box.
      : MB ICONWARNING
                                      - 0x00000040L - An icon consisting of a lowercase letter i in a circle appears in the message box.
      ; MB ICONINFORMATION
      ; MB ICONQUESTION
                                      - 0x00000020L - A guestion-mark icon appears in the message box.
      ; MB ICONERROR
                                      - 0x0000010L - A stop-sign icon appears in the message box.
      ; Установка кнопки по умолчанию
      ; MB DEFBUTTON1
                               - 0x0000000L - The first button is the default button. MB DEFBUTTON1 is the default unless
MB DEFBUTTON2, MB DEFBUTTON3, or MB DEFBUTTON4 is specified.
      : MB DEFBUTTON2
                               - 0x00000100L - The second button is the default button.
      ; MB DEFBUTTON3
                               - 0x00000200L - The third button is the default button.
      ; MB DEFBUTTON4
                               - 0x00000300L - The fourth button is the default button.
      : Возвращаемое значение в зависимости от нажатой кнопки
      : IDABORT
                         - 3 - The Abort button was selected
      ; IDCANCEL
                        - 2 - The Cancel button was selected
      ; IDCONTINUE
                        - 11 - The Continue button was selected
      : IDIGNORE
                        - 5 - The Ignore button was selected
      : IDNO
                        - 7 - The No button was selected
      : IDOK
                        - 1 - The OK button was selected
      ; IDRETRY
                        - 4 - The Retry button was selected
      ; IDTRYAGAIN
                        - 10 - The Try Again button was selected
      : IDYES
                         - 6 - The Yes button was selected
```

```
push MB_RETRYCANCEL + MB_ICONINFORMATION
                                                       ; Параметр набора кнопок
      push offset MsgBoxCaption
                                                       ; Параметр "адрес заголовка"
      push offset InputValue
                                                       ; Параметр "адрес текста сообщения"
                                                       ; Параметр "родительское окно" - NULL
      push 0
            MessageBox
                                                       ; Вызов АРІ-функции вывода сообщения на экран
      call
            EAX, 4
      cmp
            start
     jΖ
     jmp
            exit
InputError:
      push MB_YESNO + MB_ICONERROR
                                           ; Параметр набора кнопок
      push offset MsqBoxCaption
                                           ; Параметр "адрес заголовка"
                                           ; Параметр "адрес текста сообщения"
      push offset ValueInputError
                                           ; Параметр "родительское окно" - NULL
      push 0
            MessageBox
                                                 ; Вызов АРІ-функции вывода сообщения на экран
      call
           EAX, 6
      cmp
            start
     jΖ
exit:
                              ; Пустой параметр для функции выхода
      push 0
                              ; Вызов АРІ-функции выхода
      call
            ExitProcess
```

end start

Иконки для диалогового окна

Icon Flag values



MB_ICONHAND, MB_ICONSTOP, or MB_ICONERROR



MB_ICONQUESTION



MB_ICONEXCLAMATION or MB_ICONWARNING



MB_ICONASTERISK or MB_ICONINFORMATION

Prototypes.inc

; InputBox Prototype

; Функция возвращает в ЕАХ длину введённого текста

; В случае ошибки, функция возвращает 0

InputBox PROTO IB_SCText:DWORD,\ ; Текст, показываемый в окне InputBox

IB_Caption:DWORD,\; Заголовок окна InputBox

IB_Buffer: DWORD ; Контейнер для введённого текста