# উবুন্টু(লিনাক্স)-এ নেটওয়ার্ক ইন্টারফেসের নাম কিভাবে দেখবেন?

উবুন্টু(লিনাক্স) অপারেটিং সিস্টেম চালিত একটি কম্পিউটারে বর্তমানে কী কী নেটওয়ার্ক ইন্টারফেস আছে তা জানতে কনসোলে নিম্নলিখিত নির্দেশনা প্রদান করুন:

### নির্দেশনা ১:

```
$ ip link show
```

```
admin@mypc:~$ ip link show
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 16436 qdisc noqueue state UNKNOWN
    link/loopback 00:00:00:00:00 brd 00:00:00:00:00
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP qlen 1000
    link/ether 00:1c:c0:b9:1d:2d brd ff:ff:ff:ff:ff
```

# নির্দেশনা ২:

```
$ ifconfig -s -a
```

```
admin@mypc:~
admin@mypc:~$ ifconfig -s -a
       MTU Met
                  RX-OK RX-ERR RX-DRP RX-OVR
                                                 TX-OK TX-ERR TX-DRP TX-OVR Flg
Iface
           1500 0
                       5681
                                  0
                                         0 0
                                                       5696
                                                                 0
                                                                        0
                                                                                 BMRU
          16436 0
                                  0
                                         0 0
                                                                 0
                                                                        0
                                                                                0 LRU
```

# <u>নির্দেশনা ৩:</u>

```
$ netstat -i
```

```
admin@mypc:~
admin@mypc:~$ netstat -i
Kernel Interface table
Iface
        MTU Met
                  RX-OK RX-ERR RX-DRP RX-OVR
                                                   TX-OK TX-ERR TX-DRP TX-OVR Flg
           1500 0
                        5675
                                   0
                                                        5687
                                                                   0
                                                                                   BMRU
                                   0
                                          0 0
                                                                   0
          16436 0
                          91
                                                                          0
                                                                                  0 LRU
```

#### নিৰ্দেশনা ৪:

\$ ls /sys/class/net

```
admin@mypc:~
admin@mypc:~$ ls /sys/class/net
eth0 lo
```

### নির্দেশনা ৫:

\$ sudo lshw -class network

```
admin@mypc:~
admin@mypc:~$ sudo lshw -class network
  *-network
      description: Ethernet interface
      product: BCM4401-B0 100Base-TX
      vendor: Broadcom Corporation
       physical id: 0
       bus info: pci@0000:03:00.0
      version: 02
      size: 10MB/s
      capacity: 100MB/s
      width: 32 bits
      clock: 33MHz
      capabilities: (snipped for brevity)
      configuration: (snipped for brevity)
       resources: irq:17 memory:ef9fe000-ef9fffff
```