



ConnectWise Manage

API Access

This guide walks you through creating an API key in ConnectWise Manage so Rev.io can securely pull your data for migration. The process takes about 10 minutes and does not require any software installation.

What We Need From You

ITEM	DESCRIPTION	EXAMPLE
Site URL	The domain of your ConnectWise instance	na.myconnectwise.net
Company ID	The company name used on the login screen	yourcompanyname
Public Key	Generated in Step 4	aBcDeFgHiJkLmNoP
Private Key	Generated in Step 4 — shown once only	aBcDeFgHiJkLmNoP

🔒 These credentials provide **read-only access**. Rev.io will not use them to make any changes to your system.

Setup Steps

- Find Your Site URL and Company ID**
Log into ConnectWise Manage. Look at the address bar — your URL will look like:

https://na.myconnectwise.net/v4_6_release/ConnectWise.aspx

- **Site URL:**

the domain portion, e.g. `na.myconnectwise.net`

- **Company ID:**

the name you type in the *Company* field on the login screen

2

Create an API Member Account

An API Member is a special non-login account for API access. It does not consume a regular user license.

- Go to

System → Members

and click

+

to create a new member.

- Set

Member ID

to `APIIntegration` (or any name you prefer).

- Set

License Class

to `API` (not Full or Non-billable).

- Assign the security role created in Step 3, then click

Save

.

3

Create a Security Role with Read Permissions

Create a role called `API Read Only` under

System → Security Roles

and enable

Inquire (read)

access for the following:

CATEGORY	SECTIONS
Companies	Companies, Contacts, Configurations, Sites

CATEGORY	SECTIONS
Finance	Agreements, Invoices, Billing Terms, Tax Codes
Procurement	Products, Product Catalog
Service Desk	Tickets, Boards, Priorities
Sales	Opportunities, Activities
Time & Expense	Time Entries, Expense Entries
Schedule	Schedule Entries
System	Members, Locations

After saving the role, go back to the API Member and assign it.

4

Generate API Keys

- While viewing the API Member record, click the **API Keys** tab.
- Click **+** to generate a new key pair; give it a description such as `Rev.io Data Migration`.
- Click **Save**.



ConnectWise will display the **Public Key** and **Private Key**.

Copy both immediately

— the Private Key is only shown once and cannot be retrieved later.

5**Send Your Credentials to Rev.io**

Send the following to your Rev.io project contact via a secure channel (encrypted email or secure file sharing — not plain email):

Site URL: `na.myconnectwise.net`

Company ID: `yourcompanyname`

Public Key: `(from Step 4)`

Private Key: `(from Step 4)`

● Frequently Asked Questions

Will this affect my ConnectWise users or data?

No. The API key provides read-only access and does not interfere with normal ConnectWise operations.

I already have an API user set up — can I use it?

Yes. Generate an additional key pair on an existing API member, or point us to one you already have — just ensure it has the read access described in Step 3.

How do I revoke access after migration?

Go to System → Members, open the API Member, click the API Keys tab, and delete the key pair. Access is immediately revoked.

What ConnectWise version is required?

ConnectWise Manage version 2019.1 or later. Check under System → My Company → ConnectWise.