
Steps to Create an Azure Virtual Machine

1. Log into Azure Portal

1. Go to the Azure portal
2. Sign in with your Microsoft credentials.

2. Create a New Virtual Machine


1. In the Azure Portal, click on the **Create a resource** button.
2. Search for **Virtual Machine** and select it.
3. Click on the **Create** button.




3. Configure Basic Settings

Fill in the following details:


- **Subscription**: Select your Azure subscription.
- **Resource group**: Choose an existing resource group or create a new one.
- **Virtual machine name**: Enter a unique name for your VM.
- **Region**: Choose the Azure region where you want the VM to be hosted.
- **Availability options**: Select options as required.
- **Image**: Choose the operating system (e.g., *Ubuntu Server 22.04 LTS*).
- **Size**: Pick a VM size based on your needs (default: *Standard_B1s*).





4. Configure Administrator Account

- **Authentication type**: Choose either *Password* or *SSH public key*.
- **Username**: Set the admin username.
- **Password or SSH key**: Enter the password or paste the public SSH key (for Linux VMs).




5. Configure Inbound Port Rules

- **Public inbound ports**: Select *Allow selected ports*.
- **Select inbound ports**: Choose ports like:
  - **SSH (22)** for Linux VMs.
  - **HTTP (80)**
  - **HTTPS (443)**


6. Disk Configuration

- **OS disk type**: Choose between *Standard SSD*, *Premium SSD*, or *HDD*.




7. Networking


- **Virtual network**: Use the default network or create a custom one.
- **Subnet**: Select a subnet for the VM.
- **Public IP**: Enable it to access the VM via SSH




8. Review and Create

1. Click on the **Review + create** button.
2. Azure will validate the configuration.
3. Once validated, click **Create**.
4. Download the SSH Key






5. Once deployed, you can see the VM up and running.



9. Access the Virtual Machine

1. Open the Command Prompt
2. And type this command : ssh -i ~/.ssh/<key-name> <username>@your-vm-ip-address.



10. Cleanup Resources

If you no longer need the VM:

1. Select your VM and resource groups.
2. Click on **Delete**.