
Steps to Create Azure Blob Storage

1. Create a Storage Account


1. **Sign in to Azure Portal:**
    a. Go to Azure Portal
2. **Create a Storage Account:**
    a. Click **Create a resource** → search for **Storage account** → click **Create**.



3. **Configure the Storage Account:**
    a. **Subscription:** Select your subscription.
    b. **Resource group:** Choose an existing group or create a new one.
    c. **Storage account name:** Provide a unique name (lowercase, 3-24 characters).
    d. **Region:** Select a region close to you e.g. Asia Pacific (South India).
    e. **Performance:** Choose one of the following options:
        i. **Standard:** Cost-effective and suitable for general-purpose storage of unstructured data like documents, images, and backups.
        ii. **Premium:** Optimized for high-performance needs, such as storing frequently accessed data and low-latency requirements.
    f. **Redundancy:** Pick a redundancy option to determine how data is replicated:
        i. **LRS (Locally Redundant Storage):** Replicates data within a single data center in the same region.
        ii. **GRS (Geo-Redundant Storage):** Replicates data to a secondary region, providing higher durability.


iii. **ZRS (Zone-Redundant Storage):** Replicates data across multiple data centers within one region.
iv. **RA-GRS (Read-Access Geo-Redundant Storage):** Allows read access from the secondary region in addition to GRS.

g. **Create the Storage Account:**
   i. Click **Review + Create** → then **Create**.




2. Create a Blob Container

1. **Navigate to Storage Account:**
   a. Once the storage account is created, go to your **Storage Account**.
2. **Add a Container:**
   a. In the left menu, select **Containers** under **Data storage**.
   b. Click **+ Container**.
3. **Set Container Properties:**
   a. **Name:** Provide a container name.
   b. **Public access level:** Choose from:
      i. **Private (default):** No public access.
      ii. **Blob:** Public read access to blobs only.
      iii. **Container:** Public read access to blobs and the container.
4. **Create the Container:**
   a. Click **Create**.



3. Upload Blobs (Files)

1. **Access the Container:**
    a. Open your container.
2. **Upload Files:**
    a. Click **Upload**.
    b. Select files to upload.
3. **Upload:**
    a. Click **Upload**.



4. Access and Manage Blobs

- **View blob URLs:**

- Click on the blob and copy the **Blob URL**.

- **Download blobs:**
  - Select a blob and click **Download**.
- **Delete blobs:**
  - Select a blob and click **Delete**.

