

Win32 - Error Codes (1000 - 1999)



Win32 - Error Codes (6000 - 11999)



Win32 - Error Codes (2000 - 5999)

The following table provides a list of Win32 error codes.

Code	Description	Name
2000	The pixel format is invalid.	ERROR_INVALID_PIXEL_FORMAT
2001	The specified driver is invalid.	ERROR_BAD_DRIVER
2002	The window style or class attribute is invalid for this operation.	ERROR_INVALID_WINDOW_STYLE
2003	The requested metafile operation is not supported.	ERROR_METAFILE_NOT_SUPPORTED
2004	The requested transformation operation is not supported.	ERROR_TRANSFORM_NOT_SUPPORTED
2005	The requested clipping operation is not supported.	ERROR_CLIPPING_NOT_SUPPORTED
2010	The specified color management module is invalid.	ERROR_INVALID_CMM
2011	The specified color profile is invalid.	ERROR_INVALID_PROFILE
2012	The specified tag was not found.	ERROR_TAG_NOT_FOUND
2013	A required tag is not present.	ERROR_TAG_NOT_PRESENT
2014	The specified tag is already present.	ERROR_DUPLICATE_TAG
2015	The specified color profile is not associated with any device.	ERROR_PROFILE_NOT_ASSOCIATED_WITH_DEVICE
2016	The specified color profile was not found.	ERROR_PROFILE_NOT_FOUND
2017	The specified color space is invalid.	ERROR_INVALID_COLORSPACE
2018	Image Color Management is not enabled.	ERROR_ICM_NOT_ENABLED
2019	There was an error while deleting the color transform.	ERROR_DELETING_ICM_XFORM
2020	The specified color transform is invalid.	ERROR_INVALID_TRANSFORM
2021	The specified transform does not match the bitmap's color space.	ERROR_COLORSPACE_MISMATCH
2022	The specified named color index is not present in the profile.	ERROR_INVALID_COLORINDEX
2108	The network connection was made successfully, but the user had to be prompted for a password other than the one originally specified.	ERROR_CONNECTED_OTHER_PASSWORD
2202	The specified username is invalid.	ERROR_BAD_USERNAME
2250	This network connection does not exist.	ERROR_NOT_CONNECTED
2401	This network connection has files open or requests pending.	ERROR_OPEN_FILES
2402	Active connections still exist.	ERROR_ACTIVE_CONNECTIONS
2404	The device is in use by an active process and cannot be disconnected.	ERROR_DEVICE_IN_USE
3000	The specified print monitor is unknown.	ERROR_UNKNOWN_PRINT_MONITOR

		,
3001	The specified printer driver is currently in use.	ERROR_PRINTER_DRIVER_IN_USE
3002	The spool file was not found.	ERROR_SPOOL_FILE_NOT_FOUND
3003	A StartDocPrinter call was not issued.	ERROR_SPL_NO_STARTDOC
3004	An AddJob call was not issued.	ERROR_SPL_NO_ADDJOB
3005	The specified print processor has already been installed.	ERROR_PRINT_PROCESSOR_ALREADY_INSTALLED
3006	The specified print monitor has already been installed.	ERROR_PRINT_MONITOR_ALREADY_INSTALLED
3007	The specified print monitor does not have the required functions.	ERROR_INVALID_PRINT_MONITOR
3008	The specified print monitor is currently in use.	ERROR_PRINT_MONITOR_IN_USE
3009	The requested operation is not allowed when there are jobs queued to the printer.	ERROR_PRINTER_HAS_JOBS_QUEUED
3010	The requested operation is successful. Changes will not be effective until the system reboots.	ERROR_SUCCESS_REBOOT_REQUIRED
3011	The requested operation is successful. Changes will not be effective until the service is restarted.	ERROR_SUCCESS_RESTART_REQUIRED
3012	No printers were found.	ERROR_PRINTER_NOT_FOUND
4000	WINS encountered an error while processing the command.	ERROR_WINS_INTERNAL
4001	The local WINS cannot be deleted.	ERROR_CAN_NOT_DEL_LOCAL_WINS
4002	The importation from the file failed.	ERROR_STATIC_INIT
4003	The backup failed. Was a full backup done before?	ERROR_INC_BACKUP
4004	The backup failed. Check the directory to which you are backing the database .	ERROR_FULL_BACKUP
4005	The name does not exist in the WINS database.	ERROR_REC_NON_EXISTENT
4006	Replication with a nonconfigured partner is not allowed.	ERROR_RPL_NOT_ALLOWED
4100	The DHCP client has obtained an IP address that is already in use on the network. The local interface will be disabled until the DHCP client can obtain a new address.	ERROR_DHCP_ADDRESS_CONFLICT
4200	The GUID passed was not recognized as valid by a WMI data provider.	ERROR_WMI_GUID_NOT_FOUND
4201	The instance name passed was not recognized as valid by a WMI data provider.	ERROR_WMI_INSTANCE_NOT_FOUND
4202	The data item ID passed was not recognized as valid by a WMI data provider.	ERROR_WMI_ITEMID_NOT_FOUND
4203	The WMI request could not be completed and should be retried.	ERROR_WMI_TRY_AGAIN
4204	The WMI data provider could not be located.	ERROR_WMI_DP_NOT_FOUND
4205	The WMI data provider references an instance set that has not been registered.	ERROR_WMI_UNRESOLVED_INSTANCE_REF
4206	The WMI data block or event notification has already been enabled.	ERROR_WMI_ALREADY_ENABLED

ERROR_REQUEST_REFUSED

ERROR INVALID DRIVE OBJECT

The operator or administrator has

The drive identifier does not represent

refused the request.

a valid drive.

4320

4321

ERROR CLUSTERLOG CORRUPT

The cluster log is corrupt.

5029

•	0/2//24, 12.241 10		VVIII02 Elifer Codes (2000 0000)
	5030	The record could not be written to the cluster log since it exceeds the maximum size.	ERROR_CLUSTERLOG_RECORD_EXCEEDS_MAXSIZE
	5031	The cluster log exceeds its maximum size.	ERROR_CLUSTERLOG_EXCEEDS_MAXSIZE
	5032	No checkpoint record was found in the cluster log.	ERROR_CLUSTERLOG_CHKPOINT_NOT_FOUND
	5033	The minimum required disk space needed for logging is not available.	ERROR_CLUSTERLOG_NOT_ENOUGH_SPACE
	5035	A cluster network is not available for this operation.	ERROR_NETWORK_NOT_AVAILABLE
	5036	A cluster node is not available for this operation.	ERROR_NODE_NOT_AVAILABLE
	5037	All cluster nodes must be running to perform this operation.	ERROR_ALL_NODES_NOT_AVAILABLE
	5038	A cluster resource failed.	ERROR_RESOURCE_FAILED
	5039	The cluster node is not valid.	ERROR CLUSTER INVALID NODE
	5040	The cluster node already exists.	ERROR_CLUSTER_NODE_EXISTS
	5041	A node is in the process of joining the cluster.	ERROR_CLUSTER_JOIN_IN_PROGRESS
	5042	The cluster node was not found.	ERROR_CLUSTER_NODE_NOT_FOUND
	5043	The cluster local node information was not found.	ERROR_CLUSTER_LOCAL_NODE_NOT_FOUND
	5044	The cluster network already exists.	ERROR_CLUSTER_NETWORK_EXISTS
	5045	The cluster network was not found.	ERROR_CLUSTER_NETWORK_NOT_FOUND
	5046	The cluster network interface already exists.	ERROR_CLUSTER_NETINTERFACE_EXISTS
	5047	The cluster network interface was not found.	ERROR_CLUSTER_NETINTERFACE_NOT_FOUND
	5048	The cluster request is not valid for this object.	ERROR_CLUSTER_INVALID_REQUEST
	5049	The cluster network provider is not valid.	ERROR_CLUSTER_INVALID_NETWORK_PROVIDER
	5050	The cluster node is down.	ERROR_CLUSTER_NODE_DOWN
	5051	The cluster node is not reachable.	ERROR_CLUSTER_NODE_UNREACHABLE
	5052	The cluster node is not a member of the cluster.	ERROR_CLUSTER_NODE_NOT_MEMBER
	5053	A cluster join operation is not in progress.	ERROR_CLUSTER_JOIN_NOT_IN_PROGRESS
	5054	The cluster network is not valid.	ERROR_CLUSTER_INVALID_NETWORK
	5056	The cluster node is up.	ERROR_CLUSTER_NODE_UP
	5057	The cluster IP address is already in use.	ERROR_CLUSTER_IPADDR_IN_USE
	5058	The cluster node is not paused.	ERROR_CLUSTER_NODE_NOT_PAUSED
	5059	No cluster security context is available.	ERROR_CLUSTER_NO_SECURITY_CONTEXT
	5060	The cluster network is not configured for internal cluster communication.	ERROR_CLUSTER_NETWORK_NOT_INTERNAL
	5061	The cluster node is already up.	ERROR_CLUSTER_NODE_ALREADY_UP
	5062	The cluster node is already down.	ERROR_CLUSTER_NODE_ALREADY_DOWN
	5063	The cluster network is already online.	ERROR_CLUSTER_NETWORK_ALREADY_ONLINE
	5064	The cluster network is already offline.	ERROR_CLUSTER_NETWORK_ALREADY_OFFLINE
	5065	The cluster node is already a member of the cluster.	ERROR_CLUSTER_NODE_ALREADY_MEMBER

5066	The cluster network is the only one configured for internal cluster communication between two or more active cluster nodes. The internal communication capability cannot be removed from the network.	ERROR_CLUSTER_LAST_INTERNAL_NETWORK
5067	One or more cluster resources depend on the network to provide service to clients. The client access capability cannot be removed from the network.	ERROR_CLUSTER_NETWORK_HAS_DEPENDENTS
5068	This operation cannot be performed on the cluster resource as it the quorum resource. You cannot bring the quorum resource offline or modify its possible owners list.	ERROR_INVALID_OPERATION_ON_QUORUM
5069	The cluster quorum resource is not allowed to have any dependencies.	ERROR_DEPENDENCY_NOT_ALLOWED
5070	The cluster node is paused.	ERROR_CLUSTER_NODE_PAUSED
5071	The cluster resource cannot be brought online. The owner node cannot run this resource.	ERROR_NODE_CANT_HOST_RESOURCE
5072	The cluster node is not ready to perform the requested operation.	ERROR_CLUSTER_NODE_NOT_READY
5073	The cluster node is shutting down.	ERROR_CLUSTER_NODE_SHUTTING_DOWN
5074	The cluster join operation was aborted.	ERROR_CLUSTER_JOIN_ABORTED
5075	The cluster join operation failed due to incompatible software versions between the joining node and its sponsor.	ERROR_CLUSTER_INCOMPATIBLE_VERSIONS
5076	This resource cannot be created because the cluster has reached the limit on the number of resources it can monitor.	ERROR_CLUSTER_MAXNUM_OF_RESOURCES_EXCEEDED
5077	The system configuration changed during the cluster join or form operation. The join or form operation was aborted.	ERROR_CLUSTER_SYSTEM_CONFIG_CHANGED
5078	The specified resource type was not found.	ERROR_CLUSTER_RESOURCE_TYPE_NOT_FOUND
5079	The specified node does not support a resource of this type. This can be due to version inconsistencies or due to the absence of the resource DLL on this node.	ERROR_CLUSTER_RESTYPE_NOT_SUPPORTED
5080	The specified resource name is supported by this resource DLL. This can be due to a bad (or changed) name supplied to the resource DLL.	ERROR_CLUSTER_RESNAME_NOT_FOUND
5081	No authentication package could be registered with the RPC server.	ERROR_CLUSTER_NO_RPC_PACKAGES_REGISTERED
5082	You cannot bring the group online because the owner of the group is not in the preferred list for the group. To change the owner node for the group, move the group.	ERROR_CLUSTER_OWNER_NOT_IN_PREFLIST
5083	The join operation failed because the cluster database sequence number has changed or is incompatible with the locker node. This can happen during a join operation if the cluster database was changing during the join.	ERROR_CLUSTER_DATABASE_SEQMISMATCH

5084

The resource monitor will not allow the fail operation to be performed while the resource is in its current state. This can happen if the resource is in a pending state.

ERROR_RESMON_INVALID_STATE

,