

Petro-Logistics

API

Documentation



PETRO-LOGISTICS

Introduction	3
API Setup.....	4
Enable API	5
Disable API.....	5
Regenerate API Hash	6
Regenerate HTTP Password	6
Obtain Query Name	6
API Tester File.....	8
Authentication and Parameters	9
Global Parameters.....	9
Query Parameters	9
Authentication	9
List of API's Fields	10
All Fields	10
Load Date Fields.....	11
Quantity Fields.....	11
Type/Grade Fields	12
Discharge Date Fields	12
STS Fields	13
Details Fields.....	13
FS Fields.....	14
Date Fields	14
BPD Fields.....	15
Tables Legend	15
MS Excel Data Feed	16
Example File Overview	16
Example File Setup	16

Introduction

Welcome to the Petro-Logistics API Data Feed documentation. This guide will provide you with comprehensive information on how to integrate automatic updates of our data into your system using our API. With direct access to our data, you can seamlessly integrate the latest insights into your applications and data visualization tools.

The Petro-Logistics API offers automated access to our data, enabling real-time integration into your systems. The purpose of this guide is to provide developers and IT teams with the necessary documentation and code examples to seamlessly implement the API.

Petro-Logistics offers various API formats depending on each client's contract and data requirements. The most popular API formats are :

- Movements Data
- Aggregate Movements Data

Two other API formats are available:

- AggMov Data
- Mov Data.

There are also corresponding imports versions of these API formats. The imports versions differ in configuration of the parameters in that the API query looks at the discharge country and discharge date period, rather than the load country and load date period.

Each API format is associated with its own dedicated URL. See the next page of this document for the specific URLs to query.

The API supports three response formats: XML, JSON, and CSV. If no format is specified, *xml* is returned by default.

Access to the API can be managed through the Client Area. You can enable, disable, and modify API settings in the "API Management" page.



API Management

Documentation	
API Documentation	
API Client Tools	
Tester - HTML Script	
Easy - XLSX Files	Advanced - Code Examples
AggMov Data	Java Example
Aggregate Movements Data	Python Example
Imports AggMov Data	R Example
Imports Aggregate Movements Data	
Imports Mov Data	
Imports Movements Data	
Mov Data	
Movements Data	

API Setup

The API setup involves generating the necessary credentials and configuring access to the API. The following actions can be performed within the "API Management" page:

- **Enable API:** Clicking this button generates the "API Key," "API Hash," "HTTP Username," and "HTTP Password." An email will be sent to you containing your "HTTP Username" and "HTTP Password."
- **Disable API:** Clicking this button disables API access immediately.
- **Regenerate API Hash:** Clicking this button generates a new "API Hash" for enhanced security.
- **Regenerate HTTP Password:** Clicking this button automatically sends the new "HTTP Password" to your email.
- **Modify Additional Settings:** Customize additional settings as needed.

Before you can retrieve data through the API, you'll need the following:

- API Key
- API Hash
- HTTP Username
- HTTP Password
- Query Name

Access to the API Management page requires logging in at <https://secure.petro-logistics.com/client> and navigating to the "API Management" page.

The URLs relating to each API format can be seen below:

AggMov Data	https://secure.petro-logistics.com/api/v4/aggmovdata.php
Aggregate Movements Data	https://secure.petro-logistics.com/api/v4/aggregatemovementsdata.php
Imports AggMov Data	https://secure.petro-logistics.com/api/v4/importsaggmovdata.php
Imports Aggregate Movements Data	https://secure.petro-logistics.com/api/v4/importsaggregatemovementsdata.php
Imports Mov Data	https://secure.petro-logistics.com/api/v4/importsmovdata.php
Imports Movements Data	https://secure.petro-logistics.com/api/v4/importsmovementsdata.php
Mov Data	https://secure.petro-logistics.com/api/v4/movdata.php
Movements Data	https://secure.petro-logistics.com/api/v4/movementsdata.php

Enable API

1. Click "Enable API" to generate "API Key," "API Hash," "HTTP Username," and "HTTP Password."
2. You will receive a system-generated email containing your **"HTTP Username"** and your **"HTTP Password"**.

API Access Control

Use the API Key & API Hash to authorize your access to our API following our Documentation

Enable API

API Key:

API Hash:

HTTP Authentication

Use the HTTP Username & HTTP Password to authenticate your access to our API following our Documentation

HTTP Username:

HTTP Password:

Disable API

1. Click "Disable API" to immediately deactivate API access.

API Access Control

Use the API Key & API Hash to authorize your access to our API following our Documentation

Disable API

API Key:

API Hash:

Regenerate API Hash

HTTP Authentication

Use the HTTP Username & HTTP Password to authenticate your access to our API following our Documentation

HTTP Username:

HTTP Password:

Regenerate HTTP Password

Regenerate API Hash

1. Click "Regenerate API Hash" to generate a new "API Hash."

The image shows two sections of a web interface. The top section, titled "API Access Control", contains a "Disable API" button, an "API Key" input field, an "API Hash" input field, and a "Regenerate API Hash" button which is circled in red. The bottom section, titled "HTTP Authentication", contains an "HTTP Username" input field, an "HTTP Password" input field, and a "Regenerate HTTP Password" button.

Regenerate HTTP Password

1. Click "Regenerate API Password" to receive a new "API HTTP Password" via email.

The image shows two sections of a web interface. The top section, titled "API Access Control", contains a "Disable API" button, an "API Key" input field, an "API Hash" input field, and a "Regenerate API Hash" button. The bottom section, titled "HTTP Authentication", contains an "HTTP Username" input field, an "HTTP Password" input field, and a "Regenerate HTTP Password" button which is circled in red.

Obtain Query Name

1. Ask our [Support Team](#) to generate your desired queries.

2. Navigate to the API Management page on the client area and scroll to the bottom of the page to view all the API queries assigned to your account.

Queries assigned to account

Show entries


Search:

Query Name	Report Group	Report Area	Start Date	End Date	Cargo Type	API
test_1_query	E. Guinea	OPEC	2023-07-01	Most Recent		movementsdata
test_2_query	Angola	OPEC	2023-01-01	2023-01-31		aggregatemovementsdata
Query Name	Report Group	Report Area	Start Date	End Date	Cargo Type	API

Showing 1 to 2 of 2 entries

◀ Previous Next ▶

API Tester File



PETRO-LOGISTICS

API Tester - Version 4

Credentials	Options
API Key	Data Set: Choose data type...
API Hash	Format: Choose export type...
Query Name	With Headers: Choose...

Submit

* Visit the page "API Management" in your Petro-Logistics "Client Area" account, to obtain all you need!

To familiarize yourself with our API and test your authentication details, we recommend using our test API HTML file named "**pl_api_tester.html**". Follow these steps:

1. If you haven't activated your API access, enable it using the instructions above.
2. Ensure you've received the "HTTP Password" via email.
3. Download "Tester – HTML Script" on the "API Management" page, under "API Client Tools", double-click "**pl_api_tester.html**".
4. When the web page loads:
 - a. Input the provided "API Key" and "API Hash" from the "API Management" page.
 - b. Choose the desired data output format: XML, JSON, or CSV.
 - c. In the "CSV with headers (1 / 0)" field, enter 1 for headers and 0 for no headers in CSV output.
 - d. Input the relevant "Query Name" from the "API Management" page.
5. Click "Submit."
6. The second-level authentication requires your "HTTP Username" which can be found on the API Management page, as well as the "HTTP Password" sent to your email. Enter these details and click "Login."
7. View the raw data output on the opened web page.

Authentication and Parameters

Global Parameters

Parameter Name	Notes
api_key	Set in API Management
api_hash	Set in API Management

Query Parameters

Parameter Name	Notes	Default Value
format		xml
query_name	Provided query name (see "Obtain Query Name")	-
csv_with_headers	<u>Options:</u> • 0 : Do not include headers • 1 : Include headers (Option available only for csv exports)	1

Authentication

Our API uses two layers of authentication:

1. 1st Authentication Layer: HTTP Basic Authentication with a "username" and "password." You can view/reset these credentials in the "API Management" page (see "Regenerate HTTP Password").
2. 2nd Authentication Layer: Dynamic "API Key" and "API Hash." You can view/reset these credentials in the "API Management" page (see "Regenerate API Hash").

List of API's Fields

All Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
<u>Load Date Fields</u>								
tanker_name	X	X	-	-	X	X	-	-
tanker_imo	X	X	-	-	X	X	-	-
tanker_dwt	X	-	-	-	X	-	-	-
tanker_flag	X	-	-	-	X	-	-	-
tanker_owner	X	-	-	-	X	-	-	-
load_port_date	X	X	-	-	X	X	-	-
load_terminal	X	X	-	-	X	X	-	-
load_port	X	X	X	X	X	X	X	X
load_country	X	X	X	X	X	X	X	X
report_group	X	X	X	X	X	X	X	X
load_port_area	X	-	X	X	X	-	X	X
<u>Quantity fields</u>								
<u>Type/Grade fields</u>								
<u>Discharge Date fields</u>								
pc	X	O	-	-	X	X	-	-
discharge_port_date	X	O	-	-	X	X	-	-
discharge_port	X	O	X	-	X	X	X	-
second_discharge_port	X	O	-	-	X	X	-	-
via	X	O	-	-	X	X	-	-
discharge_country	X	O	X	X	X	X	X	X
discharge_area	X	-	X	X	X	-	X	X

<u>STS fields</u>								
<u>Details fields</u>								
company_estimate	X	-	-	-	X	-	-	-
supplier_note	X	-	-	-	X	-	-	-
customer_note	X	-	-	-	X	-	-	-
note	X	-	-	-	X	-	-	-
<u>FS fields</u>								
<u>Date fields</u>								
<u>BPD fields</u>								
cargo_id	X	X	-	-	X	X	-	-
parcel_id	X	-	-	-	X	-	-	-
client_cargo_status	X	X	-	-	X	X	-	-

Load Date Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
load_port_week	-	-	0	0	-	-	0	0
load_port_month	-	-	0	0	-	-	0	0
load_port_quarter	-	-	0	0	-	-	0	0

Quantity Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
qty_tonnes	X	0	X	X	X	X	X	X
qty_barrels	X	0	X	X	X	X	X	X

Type/Grade Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
c_f	X	O	-	-	X	X	-	-
cargo_type	X	O	X	X	X	X	X	X
cargo_grade	X	O	X	X	X	X	X	X
grade_estimate	X	-	-	-	X	-	-	-
api	X	-	-	-	X	X	-	-
sulphur	X	-	-	-	X	X	-	-
tan	X	-	-	-	X	X	-	-
api_category	X	-	X	X	X	X	X	X
sulphur_category	X	-	X	X	X	X	X	X
tan_category	X	-	X	X	X	X	X	X
quality_category	X	-	X	X	X	X	X	X

Discharge Date Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
discharge_port_week	-	-	O	O	-	-	O	O
discharge_port_month	-	-	O	O	-	-	O	O
discharge_port_quarter	-	-	O	O	-	-	O	O

STS Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
is_sts	X	-	X	X	X	X	X	X
sts_tanker	X	-	-	-	X	-	-	-
sts_tanker_imo	X	-	-	-	X	-	-	-
sts_discharge_port	X	-	X	X	X	-	-	-
sts_discharge_country	X	-	X	X	X	-	-	-
sts_discharge_area	X	-	X	X	X	-	-	-
sts_discharge_date	X	-	-	-	X	-	-	-
ultimate_discharge_port	X	-	X	X	X	X	X	X
ultimate_discharge_country	X	-	X	X	X	X	X	X
ultimate_discharge_area	X	-	X	X	X	X	X	X

Details Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
supplier	X	O	X	-	X	-	X	-
middle_man	X	O	X	-	X	-	X	-
customer	X	O	X	-	X	-	X	-

FS Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
fs_count	X	-	-	-	-	-	-	-
fs1_port_ref	X	-	-	-	-	-	-	-
fs1_start_date	X	-	-	-	-	-	-	-
fs1_end_date	X	-	-	-	-	-	-	-
fs2_port_ref	X	-	-	-	-	-	-	-
fs2_start_date	X	-	-	-	-	-	-	-
fs2_end_date	X	-	-	-	-	-	-	-
fs3_port_ref	X	-	-	-	-	-	-	-
fs3_start_date	X	-	-	-	-	-	-	-
fs3_end_date	X	-	-	-	-	-	-	-
fs4_port_ref	X	-	-	-	-	-	-	-
fs4_start_date	X	-	-	-	-	-	-	-
fs4_end_date	X	-	-	-	-	-	-	-
fs5_port_ref	X	-	-	-	-	-	-	-
fs5_start_date	X	-	-	-	-	-	-	-
fs5_end_date	X	-	-	-	-	-	-	-

Date Fields

	Movements	Mov	Agg. Movements	Agg. Mov	Imp. Movements	Imp. Mov	Imp. Agg. Movements	Imp. Agg. Mov
load_week	0	0	0	0	0	0	0	0
load_weekyear	0	0	0	0	0	0	0	0
load_month	0	0	0	0	0	0	0	0

load_quarter	O	O	O	O	O	O	O	O
load_year	O	O	O	O	O	O	O	O
discharge_week	O	O	O	O	O	O	O	O
discharge_weekyear	O	O	O	O	O	O	O	O
discharge_month	O	O	O	O	O	O	O	O
discharge_quarter	O	O	O	O	O	O	O	O
discharge_year	O	O	O	O	O	O	O	O

BPD Fields

			Agg.	Agg.	Imp.	Imp.	Imp.	Imp.
	Movements	Mov	Movements	Mov	Movements	Mov	Movements	Mov
qty_bpd_week	O	O	O	O	O	O	O	O
qty_bpd_month	O	O	O	O	O	O	O	O
qty_bpd_quarter	O	O	O	O	O	O	O	O
qty_bpd_year	O	O	O	O	O	O	O	O

Tables Legend

- **X** : Field present in the corresponding dataset.
- **O** : Field optionally present in corresponding dataset, depending on **user settings** or **query build** options.
- **-** : Field not present in the corresponding dataset.

MS Excel Data Feed

Example File Overview

The code used to implement this example file is VBA. This will allow anyone familiar with Visual Basic to change the functionality of this file.

Microsoft Excel allows for charts to be created on the output data from the data feed.

Below is an example of the MS Excel API Test File layout:

	A	B
1	 API V4 <i>Data Feed: Movements</i>	
2		
3		
4		
5	Query Name:	
6	Api Key:	
7	Api Hash:	
8	HTTP User:	
9	HTTP Pass:	
10	Cargo Status:	
11	Fill Table	
12		
13		
14		
15		
16	Please enable Macros before using this fi rename the INPUT and DATA work	
17		

Example File Setup

1. Download your specific data feed on the API Management page in the section “Easy – XLSX Files” of your Client Area.
2. You will then be presented with sheet 1 named “**INPUT**” (please ensure macros are enabled). Enter all authentication details in relevant fields:
 - a. API Key
 - b. API Hash
 - c. HTTP Username
 - d. HTTP Password

If your API is already activated before the download, your credentials are automatically filled in the corresponding cells.

3. Input a relevant API **Query name** that is assigned to you. Your assigned queries can be found on your API Management page. Be sure the Query name corresponds to the relevant API type (Movements Data, Aggregate Movements Data, etc.).
4. Press the button “Fill Table”.
5. Sheet 2 named “**DATA**”, will appear showing the tabulated output data from the API data feed.
6. Save the file after going through all the previous steps. Your authentication details and query name will remain in the relevant cells. When you open the file again to refresh with new data you will only need to press the Fill Table button.