


I.Cài DNS server

Bài 1 cấu hình phân giải xuôi

Bước 1: dựng 2 máy ảo ubuntu



Bước 2: cấu hình card mạng máy 1

Dùng nano mở file cấu hình card mạng

```
root@ubuntu2:~# cd /  
root@ubuntu2:/# nano etc/network/interfaces _
```

Chỉnh sửa địa chỉ ip theo yêu cầu → ctrl + O lưu lại → ctrl + x thoát → khởi động dịch vụ

```
# This file describes the network interfaces  
# and how to activate them. For more informat  
  
# The loopback network interface  
auto lo  
iface lo inet loopback
```

```
# This file describes the network interfaces
# and how to activate them. For more informat

# The loopback network interface
auto lo
iface lo inet loopback

# The primary network interface
auto eth0
iface eth0 inet static
    address 192.168.1.20
    netmask 255.255.255.0
    network 192.168.1.0
    broadcast 192.168.1.255
    gateway 192.168.1.1
    # dns-* options are implemented by th
    dns-nameservers 192.168.1.20
    dns-search ns.tranduong.com
```

```
root@ubuntu2:/# etc/init.d/networking restart
* Running etc/init.d/networking restart is deprecated because it may not enable
  again some interfaces
* Reconfiguring network interfaces... [ OK ]
root@ubuntu2:/# _
```

Bước 4: cài đặt DNS

```
root@ubuntu2:/# cd mnt/DNS/
root@ubuntu2:/mnt/DNS# ls
bind9_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
bind9utils_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
libbind9-80_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
libdns81_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
libisc83_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
libisccc80_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
libiscfg82_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
liblwres80_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
root@ubuntu2:/mnt/DNS# _
```

```
root@ubuntu2:/mnt/DNS# dpkg -i /mnt/DNS/*_
```

```
root@ubuntu2:/mnt/DNS# dpkg -i /mnt/NFS/libcap2_2.22-1ubuntu3_i386.deb _
```

```
root@ubuntu2:/mnt/DNS# dpkg -i bind9_9.8.1.dfsg.P1-4ubuntu0.5_i386.deb
```

```
#
* Starting domain name service... bind9 [ OK ]
Processing triggers for man-db ...
Processing triggers for ufw ...
Processing triggers for ureadahead ...
root@ubuntu2:/mnt/DNS#
```

Bước 5: chỉnh file cấu hình để phân giải xuôi từ tên miền ra địa chỉ ip

```
root@ubuntu2:/mnt/DNS# cd /etc/bind/
root@ubuntu2:/etc/bind# ls
bind.keys      db.empty      named.conf.default-zones  zones.rfc1918
db.0           db.local      named.conf.local
db.127         db.root       named.conf.options
db.255         named.conf    rndc.key
root@ubuntu2:/etc/bind#
```

Mở file cấu hình

```
root@ubuntu2:/etc/bind# nano named.conf.default-zones
```

Chỉnh sửa file cấu hình → ctrl +o lưu lại → ctrl +x thoát ra

```
// prime the server with knowledge of the root server
zone "." {
    type hint;
    file "/etc/bind/db.root";
};

// be authoritative for the localhost forward and reverse
// broadcast zones as per RFC 1912

zone "localhost" {
    type master;
    file "/etc/bind/db.local";
};

//===== viet them o day=====
zone "tranduong.com" {
    type master;
    file "/etc/bind/db.tranduong.com";
};
```

Copy file cấu hình có sẵn

```
root@ubuntu2:/etc/bind# cp db.local db.tranduong.com_
```

Mở file cấu hình của mình

```
root@ubuntu2:/etc/bind# nano db.tranduong.com_
```

Chỉnh sửa file cấu hình lưu lại

```
;
; BIND data file for local loopback interface
;
$TTL      604800
@         IN      SOA      ns.tranduong.com. root.localhost. (
                        2      ; Serial
                        604800 ; Refresh
                        86400  ; Retry
                        2419200 ; Expire
                        604800 ) ; Negative Cache TTL
;
@         IN      NS       ns.tranduong.com.
ns        IN      A        192.168.1.20
ftp       IN      A        10.10.10.1
www       IN      A        10.20.20.1_
```

Khởi động lại dịch vụ

```
root@ubuntu2:/etc/bind# /etc/init.d/bind9 restart_
```

```
root@ubuntu2:/etc/bind# /etc/init.d/bind9 restart
* Stopping domain name service... bind9
waiting for pid 1754 to die
[ OK ]
* Starting domain name service... bind9
[ OK ]
root@ubuntu2:/etc/bind# _
```

test

```
root@ubuntu2:/etc/bind# nslookup ns.tranduong.com
Server:          192.168.1.20
Address:         192.168.1.20#53

Name:   ns.tranduong.com
Address: 192.168.1.20
```

Làm tại máy 2

Bước 1 chỉnh cấu hình card mạng

```
root@ubuntu2:~# cd /
root@ubuntu2:/# nano etc/network/interfaces _
```

Sửa dns-nameservers đc/ip máy dns → lưu lại

```
# This file describes the network interface
# and how to activate them. For more inform

# The loopback network interface
auto lo
iface lo inet loopback

# The primary network interface
auto eth0
iface eth0 inet static
    address 192.168.1.200
    netmask 255.255.255.0
    network 192.168.1.0
    broadcast 192.168.1.255
    gateway 192.168.1.1
    # dns-* options are implemented by
    dns-nameservers 192.168.1.20
    dns-search ns.tranduong.com_
```

Khởi động dịch vụ

```
root@ubuntu2:/# etc/init.d/networking restart_
```

test

```
^C Reconfiguring network interfaces...
root@ubuntu2:/# nslookup ns.tranduong.com
Server:          192.168.1.20
Address:         192.168.1.20#53

Name:   ns.tranduong.com
Address: 192.168.1.20
```