Note: The content of the Change Bar Code Detail display varies depending on the bar code type, and not all types of bar codes provide all of the following prompts on the display.

```
Define Bar Code Detail
Mark: *C002
                       Measurement method: Row/Column
Type choices, press Enter.
  Position:
                                 1-999
   Across . . . . . . . . . . . . 10
   1-999
                                       1=CODE3OF9, 2=MSI, 3=UPC-A
 Bar code type \dots 3
                                        4=UPC-E, 5=EAN-8, 6=EAN-13
                                         7=INDUST25, 8=MATRIX25
                                        9=INTERL25, 10=CODABAR
                                        11=CODE128, 12=POSTNET
                                         13=RM4SCC, 14=JPBC
                                         15=AUSTRALIAN POSTAL
 Bar code data . . . . . . . . 12345678901
 Element . . . . . . . . . .
                                         Name
                                                               More...
F3=Exit F4=Prompt F5=Refresh F6=Change measurement method
                                                          F12=Cancel
```

Press the Roll Up (Page Down) key to see the next page of the Define Bar Code Detail display.

```
Define Bar Code Detail
                       Measurement method: Row/Column
Mark: *C002
Type choices, press Enter.
  Character supplement . . . . \theta
                                     0, 2, 5
 Offset:
   Across . . . . . . . . . . . .
                                        Number
 Degree of rotation . . . . \theta
                                        0, 90, 180, 270
 Color .... *DEFAULT *DEFAULT, 1=Blue, 2=Red
                                          3=Magenta, 4=Green, 5=Cyan
                                         6=Yellow, 7=Brown, 8=Black
  Check digit . . . . . . . . N
                                         Y=Yes, N=No
 1=Below, 2=Above, 3=No
                                          Y=Yes, N=No
 HRI font . . . . . . . . *DEFAULT
                                         *DEFAULT, 1-8, F4 for list
 Module width . . . . . *DEFAULT
                                         *DEFAULT, 0.001-0.254
 Element height . . . . . . *DEFAULT Wide to narrow ratio . . . *DEFAULT
                                         *DEFAULT, 0.01-22.75
                                          *DEFAULT, 2.00-3.00
                                                                  Bottom
F3=Exit F4=Prompt F5=Refresh F6=Change measurement method F12=Cancel
```