



TRADE COPIER FOR MT5

USER GUIDE

Get up and running in 10 minutes

Welcome to Limitless Trade Copier

Mirror every trade from one MT5 account to many.

This guide walks you through the four steps to get Limitless running. It takes about 10 minutes if you already have your MT5 accounts ready.

WHAT YOU'LL DO

1. Activate your license with the key from your purchase email.
2. Add your master account — the one you trade on manually.
3. Add one or more slave accounts — the ones that mirror your master.
4. Link them — choose how lot sizes are sized on each slave.

TIP

Before you start, make sure each MetaTrader 5 terminal is installed and logged in. Limitless connects to terminals that are already open and signed in to a broker — it doesn't install brokers for you.

IMPORTANT

MT5 must have Algo Trading enabled (the green circle in the top toolbar). If it's off, Limitless can read your account but cannot place trades on it.

1 Activate your license

The first time you run Limitless, the License dialog appears. You'll use the LTC-... key from the email we sent you after your purchase.

STEPS

1. Open Limitless Trade Copier. The License dialog appears.
2. Paste your license key into the field — it looks like LTC-LIFE-XXXX-XXXX-XXXX.
3. Click Activate. The app contacts our server and binds the license to this PC.
4. Once activated, the app launches into the main dashboard.

TIP

One license = one PC. If you change computers later, contact support and we'll move your license to the new machine. Don't try to install on a second PC with the same key — the second activation will fail and we'll get an alert.

WHAT IF I DON'T HAVE A KEY YET?

Email support@limitlesscopier.com with your payment receipt and we'll issue one. Most customers receive their key within 1 business day.

2 Add your master account

The master is the account you trade on manually. Every trade you take on the master will be mirrored to your slaves automatically.

STEPS

1. Click + Add account in the top-right of any tab.
2. In the dialog, select Master as the role.
3. Fill in your broker server (e.g. Exness-Real), login number, and investor or trade password.
4. Optionally name the account so you recognize it later (e.g. "My personal Exness").
5. Click Save. The account appears in the dashboard with a green connection dot once linked successfully.

TIP

Trade password works fine. You don't need to give Limitless your master password. The investor password (read-only) is enough if the account is your master — we only need to read positions, not place trades on it. For slaves, you need a trade-enabled password.

3 Add your slave accounts

Slaves are the accounts that will mirror your master's trades. You can add as many slaves as your license tier allows.

STEPS

1. Click + Add account again.
2. This time select Slave as the role.
3. Fill in the slave's broker server, login, and trade-enabled password (not investor — we need to place trades).
4. Save. Repeat for each additional slave.

PROP FIRM ACCOUNTS

If a slave is a funded prop firm account (FTMO, MyForexFunds, etc.), use the Prop firm settings section in the dialog to enter your firm's daily-loss and overall-loss limits. Limitless will warn you before a trade pushes the slave near those thresholds.

IMPORTANT

Disclaimer: Limitless tracks the limits you enter, but enforcement is your prop firm's responsibility. The numbers we display are guidance — always confirm against your firm's dashboard.

4 Link masters to slaves

A copy link tells Limitless which master to copy from, which slave to copy to, and how to size each trade. You can have multiple links — one master can feed many slaves, or one slave can receive from multiple masters (though that's less common).

STEPS

1. Go to the Copy links tab.
2. Click + Add link.
3. Choose your master account from the first dropdown.
4. Choose the slave account from the second.
5. Pick a lot sizing mode — see next page for what each one does.
6. Click Save. The link starts copying immediately.

LIVE BEHAVIOR

Once the link is active, every new position you open on the master appears on the slave within a fraction of a second. Closes, stop-loss changes, and take-profit changes are also mirrored.

Lot sizing modes

Five ways to size each slave trade relative to the master.

MODE	WHEN TO USE	EXAMPLE
Fixed lot	Every slave trade uses the same fixed lot size, ignoring the master.	Master opens 10; slave opens 0.10.
Multiplier	Scale master lots by a factor. Simple way to size up or down.	Master 1.0; 0.5 = slave 0.5.
Mirror	Slave uses the same lots as the master, no scaling.	Master 1.0; slave 1.0.
Risk %	Sizes slave so the dollar-risk equals X% of slave's balance.	Slave bal \$10k × 1% risk = lot for \$100 SL.
Balance %	Sizes slave proportionally to balance ratio.	Slave bal is 50% of master → slave lot is 50%.

TIP

Not sure which to pick? Mirror is the safest default if all your accounts have similar balances and risk tolerance. Risk % is the right choice if accounts have very different balances and you want consistent risk percentages.

Watching trades flow

Once links are set up, three tabs show you what's happening in real time.

DASHBOARD

The home screen. Total equity across all accounts, floating P&L, copy latency, and success rate. Open positions and recent activity are shown side-by-side. Best tab to leave on a monitor while you trade.

POSITIONS

Split-screen view: masters on the left, slaves on the right. Each position shows symbol, side, lots, entry price, and live P&L. When a slave is mirroring a master trade, they appear at the same timestamp.

ACTIVITY

Full event log. Every copy attempt, success, failure, connection event, and warning is recorded with timestamps. Filter by event type to dig into specific issues.

TIP

Copy latency shown on the dashboard is the average time between a master trade opening and the slave trade firing. Under 500 ms is normal. Over 2 seconds usually means your slave broker's server is slow or your Internet has high latency.

Editing & managing accounts

Every account you've added can be edited, paused, or deleted.

RIGHT-CLICK AN ACCOUNT

In the Accounts tab, right-click any row to bring up a menu:

1. Edit account — open the dialog to change broker, login, password, role, or display name. (You can also double-click the row to edit.)
2. Close all positions on this account — emergency stop for that one account. Closes every position immediately. Requires confirmation.
3. Delete account — permanent. Removes the account and any copy links that referenced it. Requires confirmation.

CHANGING THE PASSWORD AFTER YOUR BROKER UPDATES IT

If your broker resets your password (common on some prop firms), the account in Limitless will show a red connection dot. Right-click → Edit account → paste the new password → Save. The connection re-establishes within a few seconds.

PAUSING WITHOUT DELETING

To stop copying temporarily without removing the configuration, go to the Copy links tab and toggle the link's Enabled switch off. Toggle back on to resume.

Troubleshooting

Common issues and how to fix them.

SYMPTOM	WHAT IT MEANS	HOW TO FIX
Red connection dot	Limitless can't reach the MT5 terminal or the MT5 scope	Confirm that MT5 is open and signed in. Confirm the password
Trades open on master but not slave	The copy link isn't active, or the slave isn't connected	Open Copy Links tab → confirm the link is enabled → check connection
"License is bound to a different machine"	Trying to activate on a PC other than the one originally used for activation	Email support with original PC's name and license ID. Clear cache and restart the app
Slave's lot size looks wrong	The copy link's lot-sizing mode doesn't match the master's	Edit the link in the app → check the multiplier or mode
Engine running shows red	The internal copy engine couldn't start	Restart the app. If it persists, email support and attach the log
Copy latency over 2 seconds	Either the slave broker is slow or your internet connection is slow	Try a different broker or a faster internet connection. Most brokers have a latency test

Getting help

We're here. Reach out anytime.

Email: support@limitlesscopier.com

Response time: Within 1 business day. Urgent issues (license problems, app won't start) are usually answered within a few hours.

WHEN EMAILING SUPPORT, INCLUDE

1. Your license key (the LTC-... string from your purchase email).
2. A short description of what you were trying to do and what happened instead.
3. If the app crashed or behaved unexpectedly, attach the log files. Find them via Settings → Open log folder in the app.
4. Screenshots help a lot — even a phone photo of the screen is fine.

TIP

Trading goes wrong sometimes. Limitless mirrors your trades — it doesn't second-guess them. If a trade goes against you, that's not a bug in the copier. We're happy to help you understand WHY a specific copy behaved the way it did, but the trading decisions are yours.