

Initialize Rocket—Casual Format

Main Success Scenario

1. With the System running, the Flight Director enters the Mission Parameters File (See *Use Case 1 Initialize Launch*)
2. System Initializes each Rocket Stage (See *Use Case 1.1.1 Initialize Stage*)
3. System Initializes the Payload/Capsule (See *Use Case 1.1.2 Initialize Capsule*)
4. System finds the Rocket Parameters file name and location.
5. System goes to the Rocket Parameters file location.
6. System opens the Rocket Parameters file.
7. System reads the Rocket Parameters file.
8. System initializes the Rocket Data with the appropriate Rocket Data read in from the Rocket Parameters File
9. System queries **or** receives Initialization Status from each Stage (See *Use Case 1.1.1 Initialize Stage*)
10. System queries **or** receives Initialization Status from the Payload/Capsule (See *Use Case 1.1.2 Initialize Capsule*)
11. System returns Initialization Data to the Flight Director

Alternative Scenarios

- 2a If the System receives an Initialization Error from any of the Rocket Stages, then the System returns the Error to the Flight Director (See *Use Case 1.1.1 Initialize Stage*)
- 3a If the System receives an Initialization Error from the Payload/Capsule, then the System returns the Error to the Flight Director (See *Use Case 1.1.2 Initialize Capsule*).
- 4a,5a If the System cannot find the location where the Rocket Parameters File is located, then the System returns an Error to the Flight Director: indicating a non-legitimate file path.
- 6a If the System cannot open the Rocket Parameters file, then the System returns an Error to the Flight Director indicating unable to open the Rocket Parameters file.
- 7a If the System cannot read the Rocket Parameters File, then the System returns an Error to the Flight Director indicating unable to read the Rocket Parameters file.

- 9a If the System receives an Error from any of the Stages, then the System returns the Error to the Flight Director (See *Use Case 1.1.1 Initialize Stage*)
- 10a If the System receives an Error from the Capsule, then the System returns the Error to the Flight Director (See *Use Case 1.1.2 Initialize Capsule*)

Notes/Constraints

- 11a The System indirectly alerts the Stake Holders via an upward cascade of alerts/queries (See *Use Case 1.1.1 Initialize Stage*, *Use Case 1.1.2 Initialize Capsule*)