准备工作

下载 bitnami-lampstack-8.0.3-2-linux-x64-installer.run

工具包: bitnami-wordpress-5.7.1-0-module-linux-x64-installer.run

1.安装lamp

先用工具传入linux下,找到文件路径 ps: 我的路径是/root/

首先修改权限

```
chmod 755 bitnami-lampstack-8.0.3-2-linux-x64-installer.run
```

执行bitnami-lampstack-8.0.3-2-linux-x64-installer.run

```
./bitnami-lampstack-8.0.3-2-linux-x64-installer.run
```

一路Y

```
Select the components you want to install; clear the components you do not want to install. Click Next when you are ready to continue.

Varnish [Y/n] :Y

Zend Framework [Y/n] :Y

Symfony [Y/n] :Y

CodeIgniter [Y/n] :Y

CakePHP [Y/n] :Y

Smarty [Y/n] :Y

Laravel [Y/n] :Y

PhpMyAdmin : Y (Cannot be edited)

Is the selection above correct? [Y/n]: Y

Installation folder

Please, choose a folder to install Bitnami LAMP Stack
```

跳转出设置文件夹页面

Installation folder

Please, choose a folder to install Bitnami LAMP Stack

Select a folder [/opt/lampstack-8.0.3-2]:

```
仅将文本发送到当前选项卡
```

按回车

设置MySQL的root密码 ps:要记住后面要用

Create MySQL 'root' Account Bitnami LAMP Stack database root user creation Password : 后面就一直回车 Setup is now ready to begin installing Bitnami LAMP Stack on your computer. Do you want to continue? [Y/n]: Y 等待安装完成 Please wait while Setup installs Bitnami LAMP Stack on your computer. Installing 50% 100% 完成之后通过ip进行访问 ← → ♂ ▲ 不安全 | 192.168.101.100 as 😘 🧿 🖁 🖪 | 🛠 🖷 🥷 **bitnami** To get started with Bitnami LAMP Stack we suggest the following: 1.- Check our documentation. The stack is self-contained and independent on your system, you can find all components in your installation directory: /opt/lampstack-8.0.3-2 2.- Start the servers. Open the graphical "Manager" tool in your installation directory to start & stop the installed servers. You can also use "ctlscript.sh" from the command line prompt.

出现以上页面为成功 可以进行下一步

2.安装应用(以wordpress个人博客为例)

给权限

chmod 755 bitnami-wordpress-5.7.1-0-module-linux-x64-installer.run

运行

./bitnami-wordpress-5.7.1-0-module-linux-x64-installer.run

```
Please select the installation language

[1] English - English

[2] Spanish - Español

[3] Brazilian Portuguese - Português Brasileiro

[4] Simplified Chinese - 简体中文

[5] Korean - 한국 어

[6] Hebrew - עברית

[7] German - Deutsch

[8] Romanian - Română

[9] Russian - Русский


Please choose an option [1] :
```

选择语言选择中文	
欢迎使用 Bitnami WordPress模块 安装向导。	-
安装文件夹	-
请选择Bitnami的安装目录	
选择一个文件夹 []:	
文件夹选择到/opt/lampstack-8.0.3-2	
安装文件夹	
请选择Bitnami的安装目录	
选择一个文件夹 []: /opt/lampstack-8.0.3-2	
▼ 仅将文本发送到当前选项卡	
创建管理员帐户	
登录 [user]: luobo	
您的真实姓名 [User Name]: luobo	
Email地址 [user@example.com]: fuyu16032001@gmail.com	
Please enter the MySQL password for "root" for the existing Bitnami installation	
密码: <mark>-</mark>	
用户名密码都填自己的	
密码就是上面设置的MySQL密码	
wordPress	
请配置WordPress安装	
博客名 [luobo's Blog!]: 测试博客	
Do you want to configure mail support? [y/N]: N	
▼	
配置如下	
安装类型	
请选择使用该协议栈	
[1] 开发设置:允许更改文件权限和配置设置,可以很容易地安装插件、主题和某些应用程序的更新,但从安全角度。如果是用于开发目的或用于公司内,建议允许更改。 [2] 产品设置:如果在公共服务器上部署这个协议栈,建议结合安全性和性能来进行文件权限和配置设置。安装某些可能需要手动更改,或安装如FTP等另外的服务。 请选择选项[2]:1	
安装程序已经准备好将 Bitnami WordPress模块 安装到您的电脑。	
您确定要继续吗? [Y/n]: Y	
正在安装 Bitnami WordPress模块 至您的电脑中,请稍候。	
正在安装 0% 50% 100%	

等待安装

查看页面

地址为: http://192.168.101.100/wordpress/



进入管理界面

http://192.168.101.100/wordpress/admin



Username or Email Address	
Password	•
Remember Me	Log In
Lost your password?	

← Go to KZ

用户名为你设置的

密码是mysql的root密码