

Guest Models

Hotspot Portal:

- o The guest connects to the Guest SSID and is automatically forward to a splash screen.
- o Optional Acceptable Use Policy (AUP) Acceptance and Optional Code may Require.

Sponsored Guest Portal:

- o The Sponsored Guest Portal the connects and is forwarded to a form to fill out.
- o In this portal configurable Items such as name, company name, email address, etc.
- o The Guest must know the email address of the employee being visited to type.
- o The employee receives an email and approves or rejects the guest access.
- o In Finally, the guest receives an email with their credentials, if approved.

Lobby Ambassador:

- o An employee in reception simply creates a guest account and distributes to the guest.
- o Prints and physically hands out credentials or send through SMS Text Message or Email.

Guest Types:

Contractor:

- o Users who need access to network for extended amount of time, up to a year.
- o Contractor Type grant access for 1 to 365 days 90-day is the default value .
- o Maximum of 3 simultaneous logins and Maximum of 5 registered devices.

Daily:

- o Guests who need access to the resources on the network for just 1 to 5 days.
- o Daily access from 1 day to 5 days while the default value is 1 day (One day).
- o Maximum Three (3) logins and maximum of Five (5) devices are allowed only.

Weekly:

- o Weekly Guest is users who need access to the network for a couple of weeks.
- o Weekly Guest type provide access from 1 day to 14 days by default is 5 days.
- o Maximum Three (3) logins and maximum of Five (5) devices are allowed only.

SocialLogin:

- o Social Login provide access from 1 day to 5 Days while by default is 1 day.
- o Social Login Guest Type allowed three 3 logins and maximum of 5 devices.

Guest Sponsor Groups:

ALL_ACCOUNTS:


- o Basically, All Account Group Sponsor can manage all guest accounts.
- o These sponsors can manage all guest accounts on your ISE network.
- o All Accounts can Manage, change passwords, terminate accounts, etc.
- o Sponsors assigned to this group can manage all guest user accounts.
- o Users in this group user identity group are members of this sponsor group.

GROUP_ACCOUNTS:

- o Can manage guest accounts created by anyone within the same sponsor group.
- o Can manage guest accounts created by sponsor users from same sponsor group.
- o Can manage just the guest accounts created by sponsors from same sponsor group.
- o Users in GROUP_ACCOUNTS user identity group are members of this sponsor group.

OWN_ACCOUNTS:


- o Own Accounts, the sponsor can manage guest accounts they created only.
- o These sponsors can manage only those guest accounts that they have created.
- o Sponsors assigned to this group can manage only guest accounts they have created.
- o Users in the OWN_ACCOUNTS user identity group are members of this sponsor group.



Guest Portals:

Hotspot Guest:


- o Hotspot Guest Portal, no username required, only an optional passcode.
- o Guests are other users who require temporary access to access the network.
- o All Guest are redirected to Welcome Web page, when users click on accept button.
- o From ISE, we can create number of different guest portal based on criteria you define.



The screenshot shows the Cisco Hotspot Portal interface. At the top, there is a blue header with the Cisco logo and the text "Hotspot Portal". Below the header, the page is titled "Acceptable Use Policy" with a subtext "Please read the Acceptable Use Policy." A large text box contains the policy details, which include responsibilities for maintaining confidentiality, permitted activities like email and web browsing, and prohibited actions like high-volume data transfers and unauthorized access. At the bottom of the policy text box, there are two buttons: "Accept" (in blue) and "Decline" (in grey).

Self-Registered Guest:

- o Self-Registered Guest Portal, basically, The Guest create their own accounts.
- o The Guests are allowed to create their own accounts and access the network.
- o Self-Registered Guest are basically using their assigned username and password.



The screenshot shows the Cisco Sponsored Guest Portal interface. At the top, there is a blue header with the Cisco logo and the text "Sponsored Guest Portal". Below the header, the page is titled "Sign On" with a subtext "Welcome to the Guest Portal. Sign on with the username and password provided to you." There are two input fields: "Username:" and "Password:", each with a text box and a small icon to the right. Below the input fields, there is a blue "Sign On" button. At the bottom, there is a link that says "Don't have an account?".


Sponsored Guest Portal:

- o Sponsored Guest Portal, in this portal the sponsor creates the guest account.
- o Guest portal is a set of special web pages that provide guest services to visitors.
- o Guest portals protect your company's network from unauthorized users access.
- o Temporary visitors can connect to company's network directed to Guest portal.

The screenshot shows the Cisco Sponsored Guest Portal Sign On page. At the top, there is a Cisco logo and the text "Sponsored Guest Portal". Below this, a "Sign On" heading is followed by a welcome message: "Welcome to the Guest Portal. Sign on with the username and password provided to you." There are two input fields: "Username:" and "Password:". Below these fields is a blue "Sign On" button.


ISE Guest Service Local Web Auth:

- o Web pages & Guest Authentication are delivered by Network Devices only.
- o Local Web Authentication does not allow/support change of Authorization.
- o To enforce Authorization, Local Web Auth uses Access Control List (ACL) only.
- o It required complete local web Auth configuration on each NAD (Switch / WLC).
- o Each device has its own web portal files, Web servers, customization method.



ISE Guest Service Central Web Auth :

- o Central Web Auth web pages and Guest Authentication are delivered by ISE only.
- o Cisco ISE Guest Service Central Web Auth allow/support change of Authorization.
- o Due to which profiling & posturing service can be done for guest and allow VLAN.
- o To enforce Authorization, it uses Access Control List (ACL) as well as the VLANs.
- o The Web Auth configuration is done on Cisco Identity Service Engine (ISE).
- o Web portal , Web servers, customization method are performed on ISE centrally.



Guest Access Flow

