


Real Server Setup Lab:



Management Subnet	192.168.100.0/24
FortiGate Management IP	192.168.100.200
FortiADC Management IP	192.168.100.210
Internal Servers Subnet	192.168.1.0/24
FortiADC External Subnet	192.168.2.0/24
FortiGate Firewall External	100.0.1.0/24
FortiADC Internal IP Address	192.168.1.254
FortiADC External IP Address	192.168.2.1
FortiGate Firewall Internal IP	192.168.2.254
FortiGate Firewall External IP	100.0.1.254
SRV1 IP Address	192.168.1.1
SRV2 IP Address	192.168.1.2
SRV3 IP Address	192.168.1.3
SRV3 IP Address	192.168.1.4
Virtual Sever-1	192.168.2.100
Virtual Sever-2	192.168.2.200
FortiGate VIP-1	100.0.1.100
FortiGate VIP-2	100.0.1.200
External PC1 IP Address	100.0.1.1
External PC2 IP Address	100.0.1.2
External PC3 IP Address	100.0.1.3

From the main menu, click **Server Load Balance > Real Server Pool**. Click **Create New**

The screenshot shows the FortiGate web interface. On the left is a navigation menu with the following items: Dashboard, Security Fabric, FortiView, System, Shared Resources, Network, **Server Load Balance** (highlighted with a red box), Virtual Server, Application Resources, and Application Optimization. Below the menu is a blue bar with **Real Server Pool** (highlighted with a yellow box). The main content area has three tabs: **Real Server Pool**, **Real Server** (highlighted with a red box), and **Server SSL**. Below the tabs are buttons for **Delete**, **+ Create New** (highlighted with a red box), and **+ Add Filter**. A table header shows **Name** and **Server Type**. Below the table, it says "Showing 0 to 0 of 0 entries 0 rows selected Show 25 entries".

Fill in the required fields, Name and Address Click **OK** or **Apply** to save the real server configuration.

The screenshot shows the FortiGate web interface with the **Real Server** configuration page. The left navigation menu is the same as in the previous screenshot, with **Server Load Balance** and **Real Server Pool** highlighted. The main content area has the **Real Server** tab selected. The configuration fields are: **Name** (text box with "SRV1" entered, highlighted with a red box), **Server Type** (radio buttons: **Static** (selected), **Dynamic Manual**, **Dynamic Auto**), **Status** (radio buttons: **Enable** (selected), **Disable**, **Maintain**), **Type** (radio buttons: **IP** (selected), **FQDN**), **Address** (text box with "192.168.1.1" entered, highlighted with a red box, and a red "..." button to its right), and **Address6** (text box with "::" entered).

Dashboard

Security Fabric

FortiView

System

Shared Resources

Network

Server Load Balance

Virtual Server

Application Resources

Application Optimization

Real Server Pool

Real Server

Name

SRV2

Server Type

Static

Dynamic Manual

Dynamic Auto

Status

Enable

Disable

Maintain

Type

IP

FQDN

Address

192.168.1.2

Address6

::

Dashboard

Security Fabric

FortiView

System

Shared Resources

Network

Server Load Balance

Virtual Server

Application Resources

Application Optimization

Real Server Pool

Real Server

Name

SRV3

Server Type

Static

Dynamic Manual

Dynamic Auto

Status

Enable

Disable

Maintain

Type

IP

FQDN

Address

192.168.1.3

Address6

::

Real Server

Name

SRV4

Server Type

Static

Dynamic Manual

Dynamic Auto

Status

Enable

Disable

Maintain

Type

IP

FQDN

Address

192.168.1.4

Address6

::

Save

Cancel

Real Server Pool		Real Server	Server SSL	
 Delete		 Create New		 Add Filter
Name	Server Type	Status	Address	
SRV1	Static	Enable	192.168.1.1	
SRV2	Static	Enable	192.168.1.2	
SRV3	Static	Enable	192.168.1.3	
SRV4	Static	Enable	192.168.1.4	