


Forwarding Methods:

FortiADC offers several packet forwarding methods to handle traffic distribution and manage network traffic efficiently.


Direct Routing:

This method forwards packets directly to backend servers without modifying their IP addresses. It preserves the original client IP information, which is useful for applications that need to see the client's IP address. In this method, the FortiADC only processes the incoming request, while the response bypasses the ADC and goes directly from the real server to the client. Requires configuring the real server with a loopback alias IP.



DNAT (Destination NAT):


This method replaces the destination IP address of the incoming packet with the IP address of the selected backend server. It's useful for hiding the real IP addresses of backend servers. Typically, Layer 4 DNAT uses two interfaces connecting to client and real servers. The packet's destination IP will be changed after going through the FortiADC VS. Use DNAT as the packet forwarding method and set the default gateway on each server to FortiADC IP address.



Full-NAT:


This method modifies both the source and destination IP addresses of the packet. It's typically used in scenarios where both client and server IP addresses need to be translated.

Layer 4 FULLNAT VS changes the packet's source and destination address before sending the packet to real servers. User can self-define the pool IP address range in the NAT source pool, and select it in Pool List. Normally, the NAT source pool's address range is in the same network subnet with real server.




Tunneling:

FortiADC also supports tunneling. This allows FortiADC to send client requests to real servers through layer 4 IP tunnels. FortiADC encapsulates the original packet, with the client to virtual server IP addresses, and routes the packets to the real server. The real server will decapsulate the packet (containing the client IP to virtual server IP) and respond to the client. The real servers will be configured with a secondary IP that is the same as the virtual server.



NAT46:

Using NAT46, FortiADC replaces both the destination and source IP addresses, translating IPv4 addresses to IPv6 addresses. The source IP address is replaced by an IP address from the pool you specify. The destination IP address is replaced with the IP address of the back-end server selected by the load balancer.



NAT64:

Using NAT64, FortiADC replaces both the destination and source IP addresses, translating IPv6 addresses to IPv4 addresses. The source IP address is replaced by an IP address from the pool you specify. The destination IP address is replaced with the IP address of the back-end server selected by the load balancer.

