


DHCP

Hyper-v setup

- új virtuális gép



- gép neve
- gép helye
- Gen 2
- 4 GB RAM, X pipa

Név és hely megadása

Alapismertek

Név és hely megadása

Generáció beállítása

Memória hozzárendelése

Hálózatkezelés beállítása

Virtuális merevlemez csatlakoztatása

Telepítési beállítások

Összegzés

Itt adhatja meg a virtuális gép nevét és helyét.

A név megjelenik a Hyper-V kezelőjében. Ajánlott könnyen azonosítható nevet használni, például a vendég operációs rendszer vagy a feladat nevét.

Név:

A virtuális gép egy újonnan létrehozott vagy egy már meglévő mappába is menthető. Ha nem választ mappát, a rendszer a kiszolgálóhoz rendelt alapértelmezett mappába menti a virtuális gépet.

☒ A virtuális gép mentése más helyre

Hely: Tallózás...

⚠ Ha ellenőrzőpontokat szeretne készíteni erről a virtuális gépről, jelöljön ki elegendő szabad területtel rendelkező helyet. Az ellenőrzőpontok tartalmazzák a virtuális gépen lévő adatokat is, ezért nagy területet igényelhetnek.

- Default Switch

Alapismertek

Név és hely megadása

Generáció beállítása

Memória hozzárendelése

Hálózatkezelés beállítása

Virtuális merevlemez csatlakoztatása

Telepítési beállítások

Összegzés

Minden új virtuális gép tartalmaz egy hálózati adaptert, amely beállítható virtuális kapcsoló használatára, de kapcsolat nélküli állapotban is maradhat.

Kapcsolat:

- HDD neve
- HDD helye
- HDD nagysága

Alapismertek

Név és hely megadása

Generáció beállítása

Memória hozzárendelése

Hálózatkezelés beállítása

Virtuális merevlemez csatlakoztatása

Telepítési beállítások

Összegzés

A virtuális gépnek tárhelyre van szüksége az operációs rendszer-telepítéshez. A tárhely nagyságát meghatározhatja akár most, akár a virtuális gép tulajdonságainak későbbi módosításakor is.

☒ Virtuális merevlemez létrehozása

Ezzel a lehetőséggel dinamikusan bővülő virtuális merevlemez (VHDX) hozhat létre.

Név:

Hely: Tallózás...

Méret: GB (maximum 64 TB)

☐ Meglévő virtuális merevlemez használata

- ISO fájl

Alapismertek

Név és hely megadása

Generáció beállítása

Memória hozzárendelése

Hálózatkezelés beállítása

Virtuális merevlemez csatlakoztatása

Telepítési beállítások

Összegzés

Ha megfelelő hozzáférése van a telepítési adathordozóhoz, telepítheti most az operációs rendszert, de a telepítés később is végrehajtható.

☐ Operációs rendszer telepítése később

☒ Operációs rendszer telepítése rendszerindító lemezképfájlból

Adathordozó

Lemezképfájl (.iso): Tallózás...

☐ Operációs rendszer telepítése hálózati telepítési kiszolgálóról

Szerver 2 hálókártya

Kliensen Belső

win_server_2022_EVAL.iso

Hálózati adapter
12da-mm-belso

Hálózati adapter
Default Switch

Kezelés

Hálózati adapter

Adja meg a hálózati adapter konfigurációját, vagy távolítsa el az adaptert.

Virtuális kapcsoló:
12da-mm-belso

VLAN-azonosító

☐ Virtuális helyi hálózati azonosítás engedélyezése

A VLAN-azonosító adja meg, hogy a virtuális gép melyik virtuális helyi hálózatot használja hálózati kommunikációra ezen a hálózati adapteren keresztül.

2

Sávszélesség kezelése

☐ Sávszélesség kezelésének engedélyezése

Adja meg, hogyan használja ez a hálózati adapter a hálózati sávszélességet. A Minimális sávszélesség és a Maximális sávszélesség beállítás is megabit/másodpercenként értendő.

Hálózati adapter

Adja meg a hálózati adapter konfigurációját, vagy távolítsa el az adaptert.

Virtuális kapcsoló:
Default Switch

VLAN-azonosító

☐ Virtuális helyi hálózati azonosítás engedélyezése

A VLAN-azonosító adja meg, hogy a virtuális gép melyik virtuális helyi hálózatot használja hálózati kommunikációra ezen a hálózati adapteren keresztül.

2

Sávszélesség kezelése

☐ Sávszélesség kezelésének engedélyezése

Adja meg, hogyan használja ez a hálózati adapter a hálózati sávszélességet. A Minimális sávszélesség és a Maximális sávszélesség beállítás is megabit/másodpercenként értendő.

Minimális sávszélesség: 0 Mb/s

Maximális sávszélesség: 0 Mb/s

Utána lévő beállítás:

12da-mm-win-srv

Hardver

Kezelés

Név
12da-mm-win-srv

Integrációs szolgáltatások
Vannak felajánlott szolgáltatások

Ellenőrzőpontok
Normál

Intelligens lapozás fájljainak helye
C:\12D-Acsop\12da-mm-win-srv

Automatikus indítási művelet
Nincs

Automatikus leállítási művelet
Kikapcsolás

Automatikus indítási művelet

Mit történjen ezzel a virtuális géppel a fizikai számítógép indulásakor?

☒ Semmi

☐ Automatikus indítás, ha a gép a szolgáltatás leállításakor futott

☐ Mindig automatikusan induljon ez a virtuális gép

Automatikus indítás késleltetése

Adja meg a virtuális gépek közti erőforrásverseny elkerülését szolgáló indítási késleltetést.

Indítási késleltetés: 0 másodperc

Automatikus leállítási művelet

Mit történjen ezzel a virtuális géppel a fizikai számítógép leállításakor?

☐ Virtuális gép állapotának mentése

A Hyper-V a virtuális gép üzemi memóriájával megegyező méretű lemezterületet foglal le annak érdekében, hogy a memória kiírható legyen a lemezre a fizikai gép leállításakor.

☒ Virtuális gép kikapcsolása

☐ Vendég operációs rendszer leállítása

A vendég operációs rendszer leállítását vezérlő integrációs szolgáltatást telepíteni és engedélyezni kell a virtuális gépen.

Szerver, kliens telepítése ugyanaz


Szerveren Win AD

+ hálókártya, egy külső és egy belső




Külső hálózat:

- minden ip dhcp-ből fog kapni
- dns forwarder 192.168.100.120



Belső hálózat:

- statikusan állítjuk be




(Szerver Restart)

Kliens beléptetése:


- statikus IP
- Advanced System, Computer Name, Második Change, Domain-név

Belépet a kliens




Szerver:

- DHCP, add role
- Configál => (next, kép, next)



(Szerver Restart)

DHCP:



Nevet adunk neki:

New Scope Wizard

Scope Name
You have to provide an identifying scope name. You also have the option of providing a description.

Type a name and description for this scope. This information helps you quickly identify how the scope is to be used on your network.

Name:

Description:

Mettől-Meddig osztja ki az IP címeket:

New Scope Wizard

IP Address Range
You define the scope address range by identifying a set of consecutive IP addresses.

Configuration settings for DHCP Server

Enter the range of addresses that the scope distributes.

Start IP address:

End IP address:

Configuration settings that propagate to DHCP Client

Length:

Subnet mask:

Ha kizárólag zárt címeket:

Add Exclusions and Delay
Exclusions are addresses or a range of addresses that are not distributed by the server. A delay is the time duration by which the server will delay the transmission of a DHCP OFFER message.

Type the IP address range that you want to exclude. If you want to exclude a single address, type an address in Start IP address only.

Start IP address: End IP address:

Excluded address range:

Add Remove

Meddig tartson a cím:

Lease Duration

The lease duration specifies how long a client can use an IP address from this scope.



Lease durations should typically be equal to the average time the computer is connected to the same physical network. For mobile networks that consist mainly of portable computers or dial-up clients, shorter lease durations can be useful.

Likewise, for a stable network that consists mainly of desktop computers at fixed locations, longer lease durations are more appropriate.

Set the duration for scope leases when distributed by this server.

Limited to:

Days:	Hours:	Minutes:
8	0	0

Default-Address:

Router (Default Gateway)

You can specify the routers, or default gateways, to be distributed.

To add an IP address for a router used by clients, enter the address in the text box.

IP address:

192.168.151.126	Add
	Remove
	Up
	Down

Domain Name and DNS Servers

The Domain Name System (DNS) maps and translates domain names used by clients on your network.



You can specify the parent domain you want the client computers on your network to use for DNS name resolution.

Parent domain:

To configure scope clients to use DNS servers on your network, enter the IP addresses for those servers.

Server name:

IP address:

Add

Resolve

192.168.1.1
192.168.151.126

Remove

Up

Down

Kliens:

DHCP cím kérése után kap ip-t és eléri a szervert

(ipconfig /renew => új ip kérése)

Network and Sharing Center

Control Panel > All Control Panel Items > Network and Sharing Center

Control Panel Home

View your basic network information and set up connections

Change adapter settings

Change advanced sharing settings

Media streaming options

View your active networks

martin.inc
Domain network

Access type: No Internet access
Connections: Ethernet0

Ethernet0 Status

General

Connection

IPv4 Connectivity: No Internet access
IPv6 Connectivity: No network access
Media State: Enabled
Duration: 00:10:42
Speed: 1.0 Gbps

Details...

Activity

Sent: 113,494
Received: 91,603

Properties Disable Diagnose

Ethernet0 Properties

Networking

Connect using:
Intel(R) 82574L Gigabit Network Connection

Configure...

This connection uses the following items:

- ☒ Client for Microsoft Networks
- ☒ File and Printer Sharing for Microsoft Networks
- ☒ QoS Packet Scheduler
- ☒ Internet Protocol Version 4 (TCP/IPv4)
- ☐ Microsoft Network Adapter Multiplexor Protocol
- ☐ Microsoft LLDIP Protocol Driver
- ☒ Internet Protocol Version 6 (TCP/IPv6)

Install... Uninstall Properties

Description
Transmission Control Protocol/Internet Protocol. The default wide area network protocol that provides communication across diverse interconnected networks.

Internet Protocol Version 4 (TCP/IPv4) Properties

General Alternate Configuration

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☒ Obtain an IP address automatically
☐ Use the following IP address:

IP address:
Subnet mask:
Default gateway:

☒ Obtain DNS server address automatically
☐ Use the following DNS server addresses:

Preferred DNS server:
Alternate DNS server:

☐ Validate settings upon exit


Advanced... OK Cancel

Command Prompt

```
C:\Users\asd>ipconfig /renew  
Windows IP Configuration  
No operation can be performed on Bluetooth Network Connection while it  
Ethernet adapter Ethernet0:  
Connection-specific DNS Suffix . : martin.inc  
Link-local IPv6 Address . . . . . : fe80::4f21:c714:2835:33b4%7  
IPv4 Address. . . . . : 192.168.151.126  
Subnet Mask . . . . . : 255.255.255.128  
Default Gateway . . . . . : 192.168.151.126  
Ethernet adapter Bluetooth Network Connection:  
Media State . . . . . : Media disconnected  
Connection-specific DNS Suffix . :  
C:\Users\asd>ping 192.168.151.126  
Pinging 192.168.151.126 with 32 bytes of data:  
Reply from 192.168.151.126: bytes=32 time=1ms TTL=128  
Reply from 192.168.151.126: bytes=32 time=1ms TTL=128  
Reply from 192.168.151.126: bytes=32 time=1ms TTL=128  
Reply from 192.168.151.126: bytes=32 time=1ms TTL=128  
Ping statistics for 192.168.151.126:  
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),  
Approximate round trip times in milli-seconds:  
Minimum = 1ms, Maximum = 1ms, Average = 1ms  
C:\Users\asd>
```

NAT

- Add role: Remote access
- pipáld ki mind a 3-at



NAT

Configuration

You can enable any of the following combinations of services, or you can customize this server.

- ☐ Remote access (dial-up or VPN)
Allow remote clients to connect to this server through either a dial-up connection or a secure virtual private network (VPN) Internet connection.
- ☒ Network address translation (NAT)
Allow internal clients to connect to the Internet using one public IP address.
- ☐ Virtual private network (VPN) access and NAT
Allow remote clients to connect to this server through the Internet and local clients to connect to the Internet using a single public IP address.
- ☐ Secure connection between two private networks
Connect this network to a remote network, such as a branch office.
- ☐ Custom configuration
Select any combination of the features available in Routing and Remote Access.

Routing and Remote Access Server Setup Wizard

NAT Internet Connection

You can select an existing interface or create a new demand-dial interface for client computers to connect to the Internet.

- ☒ Use this public interface to connect to the Internet:

Network Interfaces:

Name	Description	IP Address
Belso	Intel(R) 82574L Gigab...	192.168.151.126
Kulsoo	Intel(R) 82574L Gigab...	192.168.1.111 (DHCP)

- ☐ Create a new demand-dial interface to the Internet

A demand-dial interface is activated when a client uses the Internet. Select this option if this server connects with a modem or by using the Point-to-Point Protocol over Ethernet. The Demand-Dial Interface Wizard will start at the end of this wizard.

Finish

Kliens restart

CA Command Prompt

Microsoft Windows [Version 10.0.19045.5131]
(c) Microsoft Corporation. All rights reserved.

C:\Users\asd>ipconfig

Windows IP Configuration

Ethernet adapter Ethernet0:

Connection-specific DNS Suffix . : martin.inc
Link-local IPv6 Address : fe80::4f21:c714:2835:33b4%7
IPv4 Address. : 192.168.151.100
Subnet Mask : 255.255.255.128
Default Gateway : 192.168.151.126

Ethernet adapter Bluetooth Network Connection:

Media State : Media disconnected
Connection-specific DNS Suffix . :

C:\Users\asd>ping google.com

Pinging google.com [142.251.208.142] with 32 bytes of data:
Reply from 142.251.208.142: bytes=32 time=84ms TTL=57
Reply from 142.251.208.142: bytes=32 time=109ms TTL=57
Reply from 142.251.208.142: bytes=32 time=11ms TTL=57
Reply from 142.251.208.142: bytes=32 time=17ms TTL=57

Ping statistics for 142.251.208.142:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 11ms, Maximum = 109ms, Average = 55ms

C:\Users\asd>_

Siker!!