


Initial Server Configuration

After successfully installing Microsoft Windows Server 2022 Datacenter, several initial configurations were performed using the graphical user interface (GUI) to prepare the server for the enterprise infrastructure lab environment.

Server Information

Parameter	Value
Host Name	DC01
Operating System	Microsoft Windows Server 2022 Datacenter
OS Version	10.0.20348
Build Number	20348
OS Configuration	Primary Domain Controller
OS Build Type	Multiprocessor Free
System Manufacturer	Dell Inc.
System Model	Vostro 15 3510
System Type	x64-based PC



1. Computer Name Configuration

The default computer name assigned during installation was changed to **DC01** for easier identification and management within the enterprise environment.

Configuration Procedure

1. Open **Server Manager**.
2. Select **Local Server** from the left navigation pane.
3. Click the existing **Computer Name**.
4. In the **System Properties** window, click **Change**.
5. Enter the new computer name:

DC01

6. Click **OK**.
7. Restart the server when prompted.

Result

Setting	Value
Computer Name	DC01

2. Time Zone Configuration

To ensure accurate system logging, authentication, and scheduled task execution, the server time zone was configured according to the local geographical region.

Configuration Procedure

1. Open **Server Manager**.
2. Navigate to **Local Server**.
3. Click the current **Time Zone** setting.
4. Select **Change Time Zone**.
5. Choose:

(UTC+06:00) Dhaka

6. Click **OK** to apply the changes.

Result

Setting	Value
Time Zone	(UTC+06:00) Dhaka

3. Windows Activation Verification

The operating system activation status was verified to ensure that all Windows Server features and updates would function correctly.

Configuration Procedure

1. Open **Settings**.
2. Navigate to **System** → **Activation**.
3. Confirm that Windows Server is activated.

Activation Information

Parameter	Value
Product ID	00454-60000-00001-AA053
Activation Status	Activated

Result

Microsoft Windows Server 2022 Datacenter was successfully activated.

4. Hyper-V Installation

Hyper-V was installed to provide virtualization capabilities for hosting enterprise virtual machines required for the infrastructure project.

Installation Procedure

1. Open **Server Manager**.
2. Select **Manage** → **Add Roles and Features**.
3. Click **Next** on the Before You Begin page.
4. Select **Role-based or feature-based installation**.
5. Choose the local server (**DC01**).
6. Under **Server Roles**, select **Hyper-V**.
7. Click **Add Features** when prompted.
8. Continue through the wizard using the default configuration.
9. Click **Install**.
10. Restart the server if prompted.

Result

The Hyper-V role and associated management tools were successfully installed and ready for virtual machine deployment.