
Program blocks

motor_function [FC1]

motor_function Properties							
General							
Name	motor_function	**Number**	1	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
motor_function	Void		

Network 1:


%DB4
"MC_Power_DB"
MC_Power
"DB1".db_
emergency
EN
ENO
%DB2
"Axis_1"
Axis
Status
false
Error
false
"DB1".dummy_
bool
Enable
1
StartMode
0
StopMode
%DB5
"MC_Reset_DB"
MC_Reset
EN
ENO
%DB2
"Axis_1"
Axis
Done
false
Error
false
"DB1".exe_mc_
reset
Execute
%DB7
"MC_Halt_DB"
MC_Halt
EN
ENO
%DB2
"Axis_1"
Axis
Done
false
Error
false
"DB1".exe_mc_
halt
Execute
%DB3
"MC_Home_DB"
MC_Home
EN
ENO
%DB2
"Axis_1"
Axis
Done
false
Error
false
"DB1".exe_mc_
home
Execute
0.0
Position
0
Mode
%DB6
"MC_Move
Relative_DB"
"DB1".pgm_
engraving_
completed
"DB1".pgm_
lower_limit_
switch
"DB1".pgm_cylA_
Ext
"DB1".pgm_cylA_
Ret
"DB1".pgm_cylB_
Ext
"DB1".pgm_cylB_
Ret
"DB1".pgm_
upper_limit_
switch
MC_MoveRelative
EN
ENO
%DB2
"Axis_1"
Axis
Done
false
Error
false
"DB1".exe_mc_
moverel_fwd
Execute
"DB1".moverel_
fwd_pos
Distance
72.0
Velocity
%DB8
"MC_Move
Relative_DB_1"
"DB1".pgm_
engraving_
completed
"DB1".pgm_
lower_limit_
switch
"DB1".pgm_cylA_
Ext
"DB1".pgm_cylA_
Ret
"DB1".pgm_cylB_
Ext
"DB1".pgm_cylB_
Ret
"DB1".pgm_
upper_limit_
switch
MC_MoveRelative
EN
ENO
%DB2
"Axis_1"
Axis
Done
false
Error
false
"DB1".exe_mc_
moverel_rev
Execute
"DB1".moverel_
rev_pos
Distance
72.0
Velocity
%DB11
"MC_MoveJog_
DB"
MC_MoveJog
EN
ENO
%DB2
"Axis_1"
Axis
InVelocity
false
Error
false
"DB1".exe_
jogforward
"DB1".pgm_
lower_limit_
switch
JogForward
"DB1".exe_
jogbackward
"DB1".pgm_
upper_limit_
switch
JogBackward
35.0
Velocity

Program blocks


move_to_db1 [FC2]

move_to_db1 Properties							
General							
Name	move_to_db1	**Number**	2	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					


Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
move_to_db1	Void		

Network 1: moving the proximity sensor values to db_proximity_sensor_1, 2 and so on

update this network when there is a new proximity sensor PLC tags
right now there are 20 db_proximity_sensor_1, 2 till 20 available. add new blocks at the end only everytime



Network 2: moving the solenoid valve values to db_solenoid_valve_1, 2 and so on


%Q2.1
"solenoid_valve_13"
"DB1".db_solenoid_valve_6
%Q0.1
"solenoid_valve_12"
"DB1".db_solenoid_valve_8
%Q0.2
"solenoid_valve_6"
"DB1".db_solenoid_valve_7
%Q2.2
"solenoid_valve_5"
"DB1".db_solenoid_valve_5
%Q2.6
"solenoid_valve_4"
"DB1".db_solenoid_valve_4
%Q2.7
"solenoid_valve_3"
"DB1".db_solenoid_valve_3
%Q3.0
"solenoid_valve_2"
"DB1".db_solenoid_valve_2
%Q3.1
"solenoid_valve_1"
"DB1".db_solenoid_valve_1
%Q1.0
"pul+"
"DB1".db_solenoid_valve_9
%Q1.1
"dir+"
"DB1".db_solenoid_valve_10
%Q2.0
"solenoid_valve_8"
"DB1".db_solenoid_valve_11
%Q0.3
"pot_1_dir+"
"DB1".db_solenoid_valve_12
%Q0.0
"pot_1_pulse+"
"DB1".db_solenoid_valve_13
%Q0.5
"pot_2_dir+"
"DB1".db_solenoid_valve_14
%Q2.4
"solenoid_valve_10"
"DB1".db_solenoid_valve_15
%Q2.3
"solenoid_valve_11"
"DB1".db_solenoid_valve_16
%I1.4
"Emergency"
"DB1".db_emergency
"DB1".en_mc_power
%DB59.DBX280.1
"DB_Global".manual_commands.mc_power_actual


Program blocks

solenoid_manual [FC3]

solenoid_manual Properties							
General							
Name	solenoid_manual	**Number**	3	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
solenoid_manual	Void		


Network 1:



Network 2: Manual_on


Turn on the manual_on tag for manually operating the actuators

Network 2: Manual_on (1.1 / 2.1)




Network 2: Manual_on (2.1 / 2.1)

1.1 (Page3 - 2)



Network 3:




Program blocks

pot_1_lad [FC4]


pot_1_lad Properties							
General							
Name	pot_1_lad	**Number**	4	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
▼ Temp			
Pot1_Ready	Bool		
Pot2_Ready	Bool		
Pot3_Ready	Bool		
trig3	Bool		
trig2	Bool		
trig1	Bool		
Constant			
▼ Return			
pot_1_lad	Void		


Network 1:




Network 2:




Network 3: set home on first scan




Network 4: Conv1 Commands




Network 5: <<<<<<<<<<<POT1>>>>>>>>>>>>>>>




Network 6:




Network 7:




Network 8:




Network 9: conv1 feedbacks




Network 10: Conv2 Commands




Network 11: <<<<<<<<<<<POT2>>>>>>>>>>>>>>>




Network 12:




Network 13:




Network 14: conv2 feedbacks




Network 15: Conv3 Commands




Network 16: <<<<<<<<<<<POT3>>>>>>>>>>>>>>>




Network 17:




Network 18:




Network 19:




Network 20: conv2 feedbacks



Network 21:



Network 22: first scan home reset



Program blocks


manual_off [FC5]

manual_off Properties							
General							
Name	manual_off	**Number**	5	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
manual_off	Void		


Network 1:

Network 1: (1.1 / 3.1)



Network 1: (2.1 / 3.1)


1.1 (Page5 - 2)




3.1 (Page5 - 4)

Network 1: (3.1 / 3.1)

2.1 (Page5 - 3)



Network 2:



Program blocks


void_main_sub_funcs [FC7]

void_main_sub_funcs Properties							
General							
Name	void_main_sub_funcs	**Number**	7	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					


Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
void_main_sub_funcs	Void		

Network 1: mag push clear


this network shows whether the magazine is ready to push the workpiece to the conveyor




Network 2:




Network 3:




Network 4:




Network 5: WP IN CV2 MID




Network 6:




Network 7:




Network 8: WP READY FOR CV3




Network 9:




Network 10:



Network 11:



Network 12:




Program blocks

Fc_IO [FC8]


Fc_IO Properties							
General							
Name	Fc_IO	**Number**	8	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
Fc_IO	Void		


Network 1: Pressure



Network 2: Pressure alarms




Network 3: Digital input Status




Network 4: Digital Output Status

Network 4: Digital Output Status (1.1 / 2.1)



Network 4: Digital Output Status (2.1 / 2.1)

1.1 (Page7 - 3)




Program blocks

Main [OB1]


Main Properties							
General							
Name	Main	**Number**	1	**Type**	OB	**Language**	LAD
Numbering	Automatic						
Information							
Title	"Main Program Sweep (Cycle)"	**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Initial_Call	Bool		Initial call of this OB
Remanence	Bool		=True, if remanent data are available
Temp			
Constant			


Network 1:




Network 2:




Network 3:




Network 4:




Network 5:




Network 6:




Network 7:



Network 8:



Network 9:



Program blocks

DB1 [DB1]

DB1 Properties							
General							
Name	DB1	**Number**	1	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Static									
global_emergency	Bool	false	False	True	True	True	False		
ev_start_pb	Bool	false	False	True	True	True	False		
cycle_start	Bool	false	False	True	True	True	False		
workpiece_choice	DInt	2	False	True	True	True	False		
all_actuator_ON	Bool	false	False	True	True	True	False		
regular_scenario	Bool	false	False	True	True	True	False		
cv1_start_delay	DInt	2	False	True	True	True	False		
tMag	Time	T#0ms	False	True	True	True	False		
tC6	Time	T#0ms	False	True	True	True	False		
tC10Ext	Time	T#0ms	False	True	True	True	False		
tC10Ret	Time	T#0ms	False	True	True	True	False		
TC11Ext	Time	T#0ms	False	True	True	True	False		
tc12	Time	T#0ms	False	True	True	True	False		
tQA	Time	T#0ms	False	True	True	True	False		
QA_done	Bool	false	False	True	True	True	False		
mag_push_clear	Bool	false	False	True	True	True	False		
wp_in_cv1	Bool	false	False	True	True	True	False		
wp_in_cv1_end	Bool	false	False	True	True	True	False		
wp_in_cv2_mid	Bool	false	False	True	True	True	False		
wp_in_eng_pos	Bool	false	False	True	True	True	False		
wp_ready_for_cv3	Bool	false	False	True	True	True	False		
cylA_extended	Bool	false	False	True	True	True	False		
cylA_retracted	Bool	false	False	True	True	True	False		
cylB_extended	Bool	false	False	True	True	True	False		
cylB_retracted	Bool	false	False	True	True	True	False		
mag_push_on	Bool	false	False	True	True	True	False		
QA_ok	Bool	false	False	True	True	True	False		
wp_available_mag1	Bool	false	False	True	True	True	False		
wp_available_mag2	Bool	false	False	True	True	True	False		
wp_available_mag3	Bool	false	False	True	True	True	False		
wp_available_mag4	Bool	false	False	True	True	True	False		
wp_available_mag5	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_1	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_2	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_3	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_4	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_5	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_6	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_7	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_8	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_9	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_10	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_11	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_12	Bool	false	False	True	True	True	False		
pgm_cylB_Ext	Bool	false	False	True	True	True	False		
pgm_cylB_Ret	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_13	Bool	false	False	True	True	True	False		
pgm_cylA_Ext	Bool	false	False	True	True	True	False		
pgm_cylA_Ret	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_17	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_18	Bool	false	False	True	True	True	False		
pgm_upper_limit_switch	Bool	false	False	True	True	True	False		
pgm_lower_limit_switch	Bool	false	False	True	True	True	False		
pgm_conveyor_2	Bool	false	False	True	True	True	False		
pgm_conveyor_3	Bool	false	False	True	True	True	False		
pgm_conveyor_1	Bool	false	False	True	True	True	False		
pgm_motor_on	Bool	false	False	True	True	True	False		
pgm_engraving_on	Bool	True	False	True	True	True	False		
pgm_main_valve_supply	Bool	false	False	True	True	True	False		
pgm_solenoid_valve_14	Bool	false	False	True	True	True	False		

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
pgm_engraving_completed	Bool	false	False	True	True	True	False		
manual_on	Bool	false	False	True	True	True	False		
auto_solenoid_on	Bool	false	False	True	True	True	False		
db_solenoid_valve_1	Bool	false	False	True	True	True	False		
db_solenoid_valve_2	Bool	false	False	True	True	True	False		
db_solenoid_valve_3	Bool	false	False	True	True	True	False		
db_solenoid_valve_4	Bool	false	False	True	True	True	False		
db_solenoid_valve_5	Bool	false	False	True	True	True	False		
db_solenoid_valve_6	Bool	false	False	True	True	True	False		
db_solenoid_valve_7	Bool	false	False	True	True	True	False		
db_solenoid_valve_8	Bool	false	False	True	True	True	False		
db_solenoid_valve_9	Bool	false	False	True	True	True	False		
db_solenoid_valve_10	Bool	false	False	True	True	True	False		
db_solenoid_valve_11	Bool	false	False	True	True	True	False		
db_solenoid_valve_12	Bool	false	False	True	True	True	False		
db_solenoid_valve_13	Bool	false	False	True	True	True	False		
db_solenoid_valve_14	Bool	false	False	True	True	True	False		
db_solenoid_valve_15	Bool	false	False	True	True	True	False		
db_solenoid_valve_16	Bool	false	False	True	True	True	False		
db_proximity_sensor_3	Bool	false	False	True	True	True	False		
db_proximity_sensor_4	Bool	false	False	True	True	True	False		
db_proximity_sensor_9	Bool	false	False	True	True	True	False		
db_proximity_sensor_1	Bool	false	False	True	True	True	False		
db_proximity_sensor_6	Bool	false	False	True	True	True	False		
db_proximity_sensor_10	Bool	false	False	True	True	True	False		
db_proximity_sensor_7	Bool	false	False	True	True	True	False		
db_proximity_sensor_8	Bool	false	False	True	True	True	False		
db_proximity_sensor_5	Bool	false	False	True	True	True	False		
db_proximity_sensor_11	Bool	false	False	True	True	True	False		
db_proximity_sensor_12	Bool	false	False	True	True	True	False		
db_proximity_sensor_13	Bool	false	False	True	True	True	False		
db_proximity_sensor_14	Bool	false	False	True	True	True	False		
db_proximity_sensor_15	Bool	false	False	True	True	True	False		
db_proximity_sensor_16	Bool	false	False	True	True	True	False		
db_proximity_sensor_17	Bool	false	False	True	True	True	False		
db_proximity_sensor_18	Bool	false	False	True	True	True	False		
db_proximity_sensor_19	Bool	false	False	True	True	True	False		
db_proximity_sensor_2	Bool	false	False	True	True	True	False		
db_proximity_sensor_20	Bool	false	False	True	True	True	False		
db_proximity_sensor_21	Bool	false	False	True	True	True	False		
db_proximity_sensor_22	Bool	false	False	True	True	True	False		
db_proximity_sensor_23	Bool	false	False	True	True	True	False		
db_proximity_sensor_24	Bool	false	False	True	True	True	False		
db_conveyor_2	Bool	false	False	True	True	True	False		
db_conveyor_3	Bool	false	False	True	True	True	False		
db_conveyor_1	Bool	false	False	True	True	True	False		
db_motor	Bool	false	False	True	True	True	False		
db_engraving	Bool	false	False	True	True	True	False		
db_emergency	Bool	false	False	True	True	True	False		
cv_current_piece1	Bool	false	False	True	True	True	False		
manual_q_3.5	Bool	false	False	True	True	True	False		
en_mc_power	Bool	false	False	True	True	True	False		
exe_mc_reset	Bool	false	False	True	True	True	False		
exe_mc_home	Bool	false	False	True	True	True	False		
exe_mc_halt	Bool	false	False	True	True	True	False		
exe_jogforward	Bool	false	False	True	True	True	False		
exe_jogbackward	Bool	false	False	True	True	True	False		
exe_jogvelocity	DInt	0	False	True	True	True	False		
exe_mc_velocity	Bool	false	False	True	True	True	False		
exe_mc_moverelative	Bool	false	False	True	True	True	False		
exe_mc_moverel_fwd	Bool	false	False	True	True	True	False		
exe_mc_moverel_fwd_started	Bool	false	False	True	True	True	False		
exe_mc_moverel_rev	Bool	false	False	True	True	True	False		
mc_power_status	Bool	false	False	True	True	True	False		
mc_power_error	Bool	false	False	True	True	True	False		
mc_moverel_fwd_status	Bool	false	False	True	True	True	False		
mc_moverel_fwd_error	Bool	false	False	True	True	True	False		
mc_moverel_rev_status	Bool	false	False	True	True	True	False		
mc_moverel_rev_error	Bool	false	False	True	True	True	False		
rev_cmd_req	Bool	false	False	True	True	True	False		
moverel_value	Real	0.0	False	True	True	True	False		
moverel_fwd_pos	Real	-515.0	False	True	True	True	False		
moverel_rev_pos	Real	515.0	False	True	True	True	False		

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
sp_r_velocity	Bool	false	False	True	True	True	False		
sp_r_disp_move_relative	Bool	false	False	True	True	True	False		
sp_r_vel_move_relative_1	Bool	false	False	True	True	True	False		
sp_r_disp_move_abs	Bool	false	False	True	True	True	False		
sp_r_vel_move_abs	Bool	false	False	True	True	True	False		
r_actualvelocity	Bool	false	False	True	True	True	False		
r_actualposition	Bool	false	False	True	True	True	False		
cyl_a+_completed	Bool	false	False	True	True	True	False		
mag_sensor_clear	Bool	false	False	True	True	True	False		
mag_actuator_clear	Bool	false	False	True	True	True	False		
dummy_bool	Bool	false	False	False	False	False	False		
Wp_move_cv3	Bool	false	False	False	False	False	False		
WP_in_CV	Bool	false	False	False	False	False	False		


Program blocks

Fc_System [FC9]


Fc_System Properties							
General							
Name	Fc_System	**Number**	9	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
▼ Temp			
i	Int		
j	Int		
k	Int		
Constant			
▼ Return			
Fc_System	Void		


Network 1: Startup Interlocks




Network 2: Startup Healthy




Network 3:




Network 4: Workpiece selection



Network 5:




Network 6:




Network 7:

```
0001 FOR #i := 0 TO "DB_Global".System.Productqty_25mm BY 1
0002 DO
0003     IF #i <> 0 THEN
0004         "DB_Global".System."Product Data"[#i].PRODUCT_HEIGHT := 25;
0005     END_IF;
0006 END_FOR;
0007 FOR #j := "DB_Global".System.Productqty_25mm TO "DB_Global".System."Total products" BY 1
0008 DO
0009     IF #j <> "DB_Global".System.Productqty_25mm THEN
0010         "DB_Global".System."Product Data"[#j].PRODUCT_HEIGHT := 50;
0011     END_IF;
0012 END_FOR;
0013 FOR #k := "DB_Global".System."Total products" TO 16 BY 1
0014 DO
0015     IF #k <> "DB_Global".System."Total products" THEN
0016         "DB_Global".System."Product Data"[#k].PRODUCT_HEIGHT := 0;
0017     END_IF;
0018 END_FOR;
0019
0020
```


Network 8:




Network 9:



Network 10:



Network 11: INTERFACE



Program blocks

DB_Global [DB59]

DB_Global Properties							
General							
Name	DB_Global	**Number**	59	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Offset	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Static										
System	Struct	0.0		False	True	True	True	False		
Start_interlocks	Struct	0.0		False	True	True	True	False		
Air_Pressure_ok	Bool	0.0	false	False	True	True	True	False		
ENGV_Plate_Home	Bool	0.1	false	False	True	True	True	False		
All_Cylinders_Home	Bool	0.2	false	False	True	True	True	False		
Emergency Healthy	Bool	0.3	false	False	True	True	True	False		
Startup_Healthy	Bool	2.0	false	False	True	True	True	False		
Product Data	Array[0..16] of "product"	4.0		False	True	True	True	False		
Product Data[0]	"product"	4.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	4.0	0	False	True	True	True	False		
TARGET_QTY	Int	6.0	0	False	True	True	True	False		
MODE_SELECT	Int	8.0	0	False	True	True	True	False		
Product Data[1]	"product"	10.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	10.0	0	False	True	True	True	False		
TARGET_QTY	Int	12.0	0	False	True	True	True	False		
MODE_SELECT	Int	14.0	0	False	True	True	True	False		
Product Data[2]	"product"	16.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	16.0	0	False	True	True	True	False		
TARGET_QTY	Int	18.0	0	False	True	True	True	False		
MODE_SELECT	Int	20.0	0	False	True	True	True	False		
Product Data[3]	"product"	22.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	22.0	0	False	True	True	True	False		
TARGET_QTY	Int	24.0	0	False	True	True	True	False		
MODE_SELECT	Int	26.0	0	False	True	True	True	False		
Product Data[4]	"product"	28.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	28.0	0	False	True	True	True	False		
TARGET_QTY	Int	30.0	0	False	True	True	True	False		
MODE_SELECT	Int	32.0	0	False	True	True	True	False		
Product Data[5]	"product"	34.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	34.0	0	False	True	True	True	False		
TARGET_QTY	Int	36.0	0	False	True	True	True	False		
MODE_SELECT	Int	38.0	0	False	True	True	True	False		
Product Data[6]	"product"	40.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	40.0	0	False	True	True	True	False		
TARGET_QTY	Int	42.0	0	False	True	True	True	False		
MODE_SELECT	Int	44.0	0	False	True	True	True	False		
Product Data[7]	"product"	46.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	46.0	0	False	True	True	True	False		
TARGET_QTY	Int	48.0	0	False	True	True	True	False		
MODE_SELECT	Int	50.0	0	False	True	True	True	False		
Product Data[8]	"product"	52.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	52.0	0	False	True	True	True	False		
TARGET_QTY	Int	54.0	0	False	True	True	True	False		
MODE_SELECT	Int	56.0	0	False	True	True	True	False		
Product Data[9]	"product"	58.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	58.0	0	False	True	True	True	False		
TARGET_QTY	Int	60.0	0	False	True	True	True	False		
MODE_SELECT	Int	62.0	0	False	True	True	True	False		
Product Data[10]	"product"	64.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	64.0	0	False	True	True	True	False		
TARGET_QTY	Int	66.0	0	False	True	True	True	False		
MODE_SELECT	Int	68.0	0	False	True	True	True	False		
Product Data[11]	"product"	70.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	70.0	0	False	True	True	True	False		
TARGET_QTY	Int	72.0	0	False	True	True	True	False		

Name	Data type	Offset	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
MODE_SELECT	Int	74.0	0	False	True	True	True	False		
Product Data[12]	"product"	76.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	76.0	0	False	True	True	True	False		
TARGET_QTY	Int	78.0	0	False	True	True	True	False		
MODE_SELECT	Int	80.0	0	False	True	True	True	False		
Product Data[13]	"product"	82.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	82.0	0	False	True	True	True	False		
TARGET_QTY	Int	84.0	0	False	True	True	True	False		
MODE_SELECT	Int	86.0	0	False	True	True	True	False		
Product Data[14]	"product"	88.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	88.0	0	False	True	True	True	False		
TARGET_QTY	Int	90.0	0	False	True	True	True	False		
MODE_SELECT	Int	92.0	0	False	True	True	True	False		
Product Data[15]	"product"	94.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	94.0	0	False	True	True	True	False		
TARGET_QTY	Int	96.0	0	False	True	True	True	False		
MODE_SELECT	Int	98.0	0	False	True	True	True	False		
Product Data[16]	"product"	100.0		False	True	True	True	False		
PRODUCT_HEIGHT	Int	100.0	0	False	True	True	True	False		
TARGET_QTY	Int	102.0	0	False	True	True	True	False		
MODE_SELECT	Int	104.0	0	False	True	True	True	False		
Product_Number	Int	106.0	0	False	True	True	True	True		
Productqty_25mm	Int	108.0	0	False	True	True	True	False		
Productqty_50mm	Int	110.0	0	False	True	True	True	False		
MODE_HIGH_SPEED	Bool	112.0	false	False	True	True	True	False		
HIGH_SPEED_Active	Bool	112.1	false	False	False	False	False	False		
CMD_START	Bool	112.2	false	False	True	True	True	False		
Engraving_Completed	Bool	112.3	false	False	True	True	True	False		
Total products	Int	114.0	0	False	True	True	True	False		
Cycle_Completed	Bool	116.0	false	False	True	True	True	False		
Cycle_Reset	Bool	116.1	false	False	True	True	True	False		
Comp_Status	Struct	118.0		False	True	True	True	False		
Comp1	"Comp_Status"	118.0		False	True	True	True	False		
Ok	Bool	118.0	false	False	True	True	True	False		
Low	Bool	118.1	false	False	True	True	True	False		
Empty	Bool	118.2	false	False	True	True	True	False		
Comp2	"Comp_Status"	120.0		False	True	True	True	True		
Ok	Bool	120.0	false	False	True	True	True	False		
Low	Bool	120.1	false	False	True	True	True	False		
Empty	Bool	120.2	false	False	True	True	True	False		
Comp3	"Comp_Status"	122.0		False	True	True	True	True		
Ok	Bool	122.0	false	False	True	True	True	False		
Low	Bool	122.1	false	False	True	True	True	False		
Empty	Bool	122.2	false	False	True	True	True	False		
Comp4	"Comp_Status"	124.0		False	True	True	True	True		
Ok	Bool	124.0	false	False	True	True	True	False		
Low	Bool	124.1	false	False	True	True	True	False		
Empty	Bool	124.2	false	False	True	True	True	False		
Comp5	"Comp_Status"	126.0		False	True	True	True	True		
Ok	Bool	126.0	false	False	True	True	True	False		
Low	Bool	126.1	false	False	True	True	True	False		
Empty	Bool	126.2	false	False	True	True	True	False		
IO Status	Struct	128.0		False	True	True	True	False		
Digital_Inputs	Struct	128.0		False	True	True	True	False		
Proximity_sensor1	Bool	128.0	false	False	True	True	True	False		
Proximity_sensor2	Bool	128.1	false	False	True	True	True	False		
Proximity_sensor3	Bool	128.2	false	False	True	True	True	False		
Proximity_sensor4	Bool	128.3	false	False	True	True	True	False		
Proximity_sensor5	Bool	128.4	false	False	True	True	True	False		
Proximity_sensor6	Bool	128.5	false	False	True	True	True	False		
Proximity_sensor7	Bool	128.6	false	False	True	True	True	False		
Proximity_sensor8	Bool	128.7	false	False	True	True	True	False		
Proximity_sensor9	Bool	129.0	false	False	True	True	True	False		
Proximity_sensor10	Bool	129.1	false	False	True	True	True	False		
PGM_Low_Limit	Bool	129.2	false	False	True	True	True	False		
PGM_Up_Limit	Bool	129.3	false	False	True	True	True	False		
Emergency	Bool	129.4	false	False	True	True	True	False		
Digital_Outputs	Struct	130.0		False	True	True	True	False		
Solenoid_valve1	Bool	130.0	false	False	True	True	True	False		

Name	Data type	Offset	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Solenoid_valve2	Bool	130.1	false	False	True	True	True	False		
Solenoid_valve3	Bool	130.2	false	False	True	True	True	False		
Solenoid_valve4	Bool	130.3	false	False	True	True	True	False		
Solenoid_valve5	Bool	130.4	false	False	True	True	True	False		
Solenoid_valve6	Bool	130.5	false	False	True	True	True	False		
Solenoid_valve7	Bool	130.6	false	False	True	True	True	False		
Solenoid_valve8	Bool	130.7	false	False	True	True	True	False		
Solenoid_valve9	Bool	131.0	false	False	True	True	True	False		
Solenoid_valve10	Bool	131.1	false	False	True	True	True	False		
Solenoid_valve11	Bool	131.2	false	False	True	True	True	False		
Solenoid_valve12	Bool	131.3	false	False	True	True	True	False		
Solenoid_Valve13	Bool	131.4	false	False	True	True	True	False		
Conveyor1	Bool	131.5	false	False	True	True	True	False		
Conveyor2	Bool	131.6	false	False	True	True	True	False		
Conveyor3	Bool	131.7	false	False	True	True	True	False		
▼ Analog_inputs	Struct	132.0		False	True	True	True	False		
▼ Pressure	"Analog"	132.0		False	True	True	True	False		
Value	Real	132.0	0.0	False	True	True	True	False		
Normx	Real	136.0	0.0	False	False	False	False	False		
Low Value	Real	140.0	1.0	False	True	True	True	False		
High Value	Real	144.0	5.0	False	True	True	True	False		
Low Alarm	Bool	148.0	false	False	True	True	True	False		
High Alarm	Bool	148.1	false	False	True	True	True	False		
▼ Pot_Control	Struct	150.0		False	True	True	True	False		
▼ Conv1	"Pot_Control"	150.0		False	True	True	True	False		
Set_HighSpeed	Bool	150.0	false	False	False	False	False	False		
HighSpeed_Position	Real	152.0	30.0	False	False	False	False	False		
HighSpeed_Velocity	Real	156.0	180.0	False	False	False	False	False		
LowSpeed_Position	Real	160.0	30.0	False	False	False	False	False		
LowSpeed_Velocity	Real	164.0	180.0	False	False	False	False	False		
Set_Position	Real	168.0	0.0	False	False	False	False	False		
Set_Velocity	Real	172.0	0.0	False	False	False	False	False		
Goto_Position	Bool	176.0	false	False	False	False	False	False		
Set_Home	Bool	176.1	false	False	True	True	True	False		
Error_Fb	Bool	176.2	false	False	True	True	True	False		
Axis_Homed_Fb	Bool	176.3	false	False	True	True	True	False		
Current_Position_Fb	Real	178.0	0.0	False	True	True	True	False		
Current_Velocity_Fb	Real	182.0	0.0	False	True	True	True	False		
Reset	Bool	186.0	false	False	True	True	True	False		
▼ Conv2	"Pot_Control"	188.0		False	True	True	True	False		
Set_HighSpeed	Bool	188.0	false	False	False	False	False	False		
HighSpeed_Position	Real	190.0	150.0	False	False	False	False	False		
HighSpeed_Velocity	Real	194.0	180.0	False	False	False	False	False		
LowSpeed_Position	Real	198.0	30.0	False	False	False	False	False		
LowSpeed_Velocity	Real	202.0	180.0	False	False	False	False	False		
Set_Position	Real	206.0	0.0	False	False	False	False	False		
Set_Velocity	Real	210.0	0.0	False	False	False	False	False		
Goto_Position	Bool	214.0	false	False	False	False	False	False		
Set_Home	Bool	214.1	false	False	True	True	True	False		
Error_Fb	Bool	214.2	false	False	True	True	True	False		
Axis_Homed_Fb	Bool	214.3	false	False	True	True	True	False		
Current_Position_Fb	Real	216.0	0.0	False	True	True	True	False		
Current_Velocity_Fb	Real	220.0	0.0	False	True	True	True	False		
Reset	Bool	224.0	false	False	True	True	True	False		
▼ Conv3	"Pot_Control"	226.0		False	True	True	True	False		
Set_HighSpeed	Bool	226.0	false	False	False	False	False	False		
HighSpeed_Position	Real	228.0	150.0	False	False	False	False	False		
HighSpeed_Velocity	Real	232.0	180.0	False	False	False	False	False		
LowSpeed_Position	Real	236.0	30.0	False	False	False	False	False		
LowSpeed_Velocity	Real	240.0	180.0	False	False	False	False	False		
Set_Position	Real	244.0	0.0	False	False	False	False	False		
Set_Velocity	Real	248.0	0.0	False	False	False	False	False		
Goto_Position	Bool	252.0	false	False	False	False	False	False		
Set_Home	Bool	252.1	false	False	True	True	True	False		
Error_Fb	Bool	252.2	false	False	True	True	True	False		
Axis_Homed_Fb	Bool	252.3	false	False	True	True	True	False		
Current_Position_Fb	Real	254.0	0.0	False	True	True	True	False		
Current_Velocity_Fb	Real	258.0	0.0	False	True	True	True	False		
Reset	Bool	262.0	false	False	True	True	True	False		
▼ manual_commands	Struct	264.0		False	True	True	True	False		
Solenoid_Valve1	Bool	264.0	false	False	True	True	True	False		

Name	Data type	Offset	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Solenoid_Valve2	Bool	264.1	false	False	True	True	True	False		
Solenoid_Valve3	Bool	264.2	false	False	True	True	True	False		
Solenoid_Valve4	Bool	264.3	false	False	True	True	True	False		
Solenoid_Valve5	Bool	264.4	false	False	True	True	True	False		
Solenoid_Valve6	Bool	264.5	false	False	True	True	True	False		
Solenoid_Valve7	Bool	264.6	false	False	True	True	True	False		
Solenoid_Valve8	Bool	264.7	false	False	True	True	True	False		
Solenoid_Valve9	Bool	265.0	false	False	True	True	True	False		
Solenoid_Valve10	Bool	265.1	false	False	True	True	True	False		
Solenoid_Valve11	Bool	265.2	false	False	True	True	True	False		
Solenoid_Valve12	Bool	265.3	false	False	True	True	True	False		
Solenoid_Valve13	Bool	265.4	false	False	True	True	True	False		
Conveyor1	Bool	265.5	false	False	True	True	True	False		
Conveyor2	Bool	265.6	false	False	True	True	True	False		
Conveyor3	Bool	265.7	false	False	True	True	True	False		
sim_Proximity_sensor1	Bool	266.0	false	False	True	True	True	False		
sim_Proximity_sensor2	Bool	266.1	false	False	True	True	True	False		
sim_Proximity_sensor3	Bool	266.2	false	False	True	True	True	False		
sim_Proximity_sensor4	Bool	266.3	false	False	True	True	True	False		
sim_Proximity_sensor5	Bool	266.4	false	False	True	True	True	False		
sim_Proximity_sensor6	Bool	266.5	false	False	True	True	True	False		
sim_Proximity_sensor7	Bool	266.6	false	False	True	True	True	False		
sim_Proximity_sensor8	Bool	266.7	false	False	True	True	True	False		
sim_Proximity_sensor9	Bool	267.0	false	False	True	True	True	False		
sim_Proximity_sensor10	Bool	267.1	false	False	True	True	True	False		
sim_PGM_Low_Limit	Bool	267.2	false	False	True	True	True	False		
sim_PGM_Up_Limit	Bool	267.3	false	False	True	True	True	False		
sim_Emergency	Bool	267.4	false	False	True	True	True	False		
sim_Solenoid_Valve1	Bool	267.5	false	False	True	True	True	False		
sim_Solenoid_Valve2	Bool	267.6	false	False	True	True	True	False		
sim_Solenoid_Valve3	Bool	267.7	false	False	True	True	True	False		
sim_Solenoid_Valve4	Bool	268.0	false	False	True	True	True	False		
sim_Solenoid_Valve5	Bool	268.1	false	False	True	True	True	False		
sim_Solenoid_Valve6	Bool	268.2	false	False	True	True	True	False		
sim_Solenoid_Valve7	Bool	268.3	false	False	True	True	True	False		
sim_Solenoid_Valve8	Bool	268.4	false	False	True	True	True	False		
sim_Solenoid_Valve9	Bool	268.5	false	False	True	True	True	False		
sim_Solenoid_Valve10	Bool	268.6	false	False	True	True	True	False		
sim_Solenoid_Valve11	Bool	268.7	false	False	True	True	True	False		
sim_Solenoid_Valve12	Bool	269.0	false	False	True	True	True	False		
sim_Solenoid_Valve13	Bool	269.1	false	False	True	True	True	False		
sim_Conveyor1	Bool	269.2	false	False	True	True	True	False		
sim_Conveyor2	Bool	269.3	false	False	True	True	True	False		
sim_Conveyor3	Bool	269.4	false	False	True	True	True	False		
sim_product1	Int	270.0	0	False	True	True	True	False		
sim_product2	Int	272.0	0	False	True	True	True	False		
sim_product3	Int	274.0	0	False	True	True	True	False		
sim_product4	Int	276.0	0	False	True	True	True	False		
sim_product5	Int	278.0	0	False	True	True	True	False		
sim_mc_power	Bool	280.0	false	False	True	True	True	False		
mc_power_actual	Bool	280.1	false	False	True	True	True	False		


Program blocks

void_main [FC6]


void_main Properties							
General							
Name	void_main	**Number**	6	**Type**	FC	**Language**	LAD
Numbering	Automatic						
Information							
Title		**Author**		**Comment**		**Family**	
Version	0.1	**User-defined ID**					

Name	Data type	Default value	Comment
Input			
Output			
InOut			
Temp			
Constant			
▼ Return			
void_main	Void		


Network 1: CYCLE START




Network 2: MAG PUSH ON




Network 3: CONVEYOR 1 ON




Network 4: SOLENOID VALVE 6 ON




Network 5:




Network 6:




Network 7: CYLA EXT




Network 8:




Network 9:



Network 10:




Network 11:




Network 12:


Network 13:




Network 14:




Network 15: SOLENOID VALVE 11



Network 16:


%M2.5
"STOP_CONV3"
%DB59.DBX112.1
"DB_Global".
System.HIGH_
SPEED_Active
"DB1".db_
proximity_sensor_
9
%DB14
"IEC_Timer_0_DB_
1"
TP
Time
IN
Q
T#5S
PT
ET
T#0ms
"DB1".pgm_
solenoid_valve_
12
"DB1".WP_in_CV
R
%DB59.DBX112.1
"DB_Global".
System.HIGH_
SPEED_Active
"DB1".db_
proximity_sensor_
10
%DB16
"IEC_Timer_0_DB_
3"
TP
Time
IN
Q
T#5S
PT
ET
T#0ms
"DB1".pgm_
solenoid_valve_
13
"DB1".WP_in_CV
R

Network 17:


"IEC_Timer_0_DB_
1".Q
N
%M2.7
"mem5"
"IEC_Timer_0_DB_
3".Q
N
%M3.0
"mem6"
%DB59.DBX116.0
"DB_Global".
System.Cycle_
Completed
%DB59.DBX116.1
"DB_Global".
System.Cycle_
Reset
S
%DB59.DBX116.0
"DB_Global".
System.Cycle_
Completed
R

Program blocks / System blocks / Program resources

MC_Home_DB [DB3]

MC_Home_DB Properties							
General							
Name	MC_Home_DB	**Number**	3	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Home				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Reference point position of axis
Mode	Int	0	False	True	True	True	False		Homing mode
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
ReferenceMarkPosition	Real	0.0	False	True	True	True	False		Position at which the technology object was homed
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Power_DB [DB4]

MC_Power_DB Properties							
General							
Name	MC_Power_DB	**Number**	4	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Power				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Enable	Bool	false	False	True	True	True	False		Enable axis
StartMode	Int	1	False	True	True	True	False		Start mode on enabling of axis
StopMode	Int	0	False	True	True	True	False		Stop mode when disabling axis
▼ Output									
Status	Bool	false	False	True	True	True	False		Axis is enabled
Busy	Bool	false	False	True	True	True	False		MC_Power is active
Error	Bool	false	False	True	True	True	False		Error at MC_Power or associated technology object
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Reset_DB [DB5]

MC_Reset_DB Properties							
General							
Name	MC_Reset_DB	**Number**	5	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Reset				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Restart	Bool	false	False	True	True	True	False		Execute axis restart
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_MoveRelative_DB [DB6]

MC_MoveRelative_DB Properties							
General							
Name	MC_MoveRelative_DB	**Number**	6	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvRel				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_PositioningAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Distance	Real	0.0	False	True	True	True	False		Traversing path of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Halt_DB [DB7]

MC_Halt_DB Properties							
General							
Name	MC_Halt_DB	**Number**	7	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Halt				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_SpeedAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_MoveRelative_DB_1 [DB8]

MC_MoveRelative_DB_1 Properties							
General							
Name	MC_MoveRelative_DB_1	**Number**	8	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvRel				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Positionin-gAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Distance	Real	0.0	False	True	True	True	False		Traversing path of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_2 [DB9]

IEC_Timer_0_DB_2 Properties							
General							
Name	IEC_Timer_0_DB_2	**Number**	9	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB [DB10]

IEC_Timer_0_DB Properties							
General							
Name	IEC_Timer_0_DB	**Number**	10	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

MC_MoveJog_DB [DB11]

MC_MoveJog_DB Properties							
General							
Name	MC_MoveJog_DB	**Number**	11	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvJog				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_SpeedAxis		False	False	False	False	False		Used technology object "Axis"
JogForward	Bool	false	False	True	True	True	False		Jogging in positive direction
JogBackward	Bool	false	False	True	True	True	False		Jogging in negative direction
Velocity	Real	10.0	False	True	True	True	False		Target velocity of axis
PositionControlled	Bool	true	False	True	True	True	False		Position-controlled mode
▼ Output									
InVelocity	Bool	false	False	True	True	True	False		Target velocity of axis was reached
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_MoveJog_DB_1 [DB12]

MC_MoveJog_DB_1 Properties							
General							
Name	MC_MoveJog_DB_1	**Number**	12	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvJog				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_SpeedAxis		False	False	False	False	False		Used technology object "Axis"
JogForward	Bool	false	False	True	True	True	False		Jogging in positive direction
JogBackward	Bool	false	False	True	True	True	False		Jogging in negative direction
Velocity	Real	10.0	False	True	True	True	False		Target velocity of axis
PositionControlled	Bool	true	False	True	True	True	False		Position-controlled mode
▼ Output									
InVelocity	Bool	false	False	True	True	True	False		Target velocity of axis was reached
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Reset_DB_1 [DB13]

MC_Reset_DB_1 Properties							
General							
Name	MC_Reset_DB_1	**Number**	13	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Reset				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Restart	Bool	false	False	True	True	True	False		Execute axis restart
Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_1 [DB14]

IEC_Timer_0_DB_1 Properties							
General							
Name	IEC_Timer_0_DB_1	**Number**	14	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_6 [DB15]

IEC_Timer_0_DB_6 Properties							
General							
Name	IEC_Timer_0_DB_6	**Number**	15	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_3 [DB16]

IEC_Timer_0_DB_3 Properties							
General							
Name	IEC_Timer_0_DB_3	**Number**	16	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_8 [DB17]

IEC_Timer_0_DB_8 Properties							
General							
Name	IEC_Timer_0_DB_8	**Number**	17	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_9 [DB18]

IEC_Timer_0_DB_9 Properties							
General							
Name	IEC_Timer_0_DB_9	**Number**	18	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_10 [DB19]

IEC_Timer_0_DB_10 Properties							
General							
Name	IEC_Timer_0_DB_10	**Number**	19	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_16 [DB25]

IEC_Timer_0_DB_16 Properties							
General							
Name	IEC_Timer_0_DB_16	**Number**	25	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

Pot1_Power [DB26]

Pot1_Power Properties							
General							
Name	Pot1_Power	**Number**	26	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Power				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Enable	Bool	false	False	True	True	True	False		Enable axis
StartMode	Int	1	False	True	True	True	False		Start mode on enabling of axis
StopMode	Int	0	False	True	True	True	False		Stop mode when disabling axis
▼ Output									
Status	Bool	false	False	True	True	True	False		Axis is enabled
Busy	Bool	false	False	True	True	True	False		MC_Power is active
Error	Bool	false	False	True	True	True	False		Error at MC_Power or associated technology object
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot1_Relative [DB27]

Pot1_Relative Properties							
General							
Name	Pot1_Relative	**Number**	27	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvRel				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_PositioningAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Distance	Real	0.0	False	True	True	True	False		Traversing path of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_21 [DB30]

IEC_Timer_0_DB_21 Properties							
General							
Name	IEC_Timer_0_DB_21	**Number**	30	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_22 [DB31]

IEC_Timer_0_DB_22 Properties							
General							
Name	IEC_Timer_0_DB_22	**Number**	31	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_24 [DB33]

IEC_Timer_0_DB_24 Properties							
General							
Name	IEC_Timer_0_DB_24	**Number**	33	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_25 [DB34]

IEC_Timer_0_DB_25 Properties							
General							
Name	IEC_Timer_0_DB_25	**Number**	34	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_26 [DB35]

IEC_Timer_0_DB_26 Properties							
General							
Name	IEC_Timer_0_DB_26	**Number**	35	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_27 [DB36]

IEC_Timer_0_DB_27 Properties							
General							
Name	IEC_Timer_0_DB_27	**Number**	36	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

Pot1_Reset [DB37]

Pot1_Reset Properties							
General							
Name	Pot1_Reset	**Number**	37	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Reset				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Restart	Bool	false	False	True	True	True	False		Execute axis restart
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_29 [DB38]

IEC_Timer_0_DB_29 Properties							
General							
Name	IEC_Timer_0_DB_29	**Number**	38	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

Pot1_Jog [DB39]

Pot1_Jog Properties							
General							
Name	Pot1_Jog	**Number**	39	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvJog				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_SpeedAxis		False	False	False	False	False		Used technology object "Axis"
JogForward	Bool	false	False	True	True	True	False		Jogging in positive direction
JogBackward	Bool	false	False	True	True	True	False		Jogging in negative direction
Velocity	Real	10.0	False	True	True	True	False		Target velocity of axis
PositionControlled	Bool	true	False	True	True	True	False		Position-controlled mode
▼ Output									
InVelocity	Bool	false	False	True	True	True	False		Target velocity of axis was reached
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot1_Home [DB40]

Pot1_Home Properties							
General							
Name	Pot1_Home	**Number**	40	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Home				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Reference point position of axis
Mode	Int	0	False	True	True	True	False		Homing mode
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
ReferenceMarkPosition	Real	0.0	False	True	True	True	False		Position at which the technology object was homed
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_33 [DB42]

IEC_Timer_0_DB_33 Properties							
General							
Name	IEC_Timer_0_DB_33	**Number**	42	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_34 [DB43]

IEC_Timer_0_DB_34 Properties							
General							
Name	IEC_Timer_0_DB_34	**Number**	43	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

Pot2_Power [DB44]

Pot2_Power Properties							
General							
Name	Pot2_Power	**Number**	44	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Power				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Enable	Bool	false	False	True	True	True	False		Enable axis
StartMode	Int	1	False	True	True	True	False		Start mode on enabling of axis
StopMode	Int	0	False	True	True	True	False		Stop mode when disabling axis
▼ Output									
Status	Bool	false	False	True	True	True	False		Axis is enabled
Busy	Bool	false	False	True	True	True	False		MC_Power is active
Error	Bool	false	False	True	True	True	False		Error at MC_Power or associated technology object
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_36 [DB45]

IEC_Timer_0_DB_36 Properties							
General							
Name	IEC_Timer_0_DB_36	**Number**	45	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_37 [DB46]

IEC_Timer_0_DB_37 Properties							
General							
Name	IEC_Timer_0_DB_37	**Number**	46	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_38 [DB47]

IEC_Timer_0_DB_38 Properties							
General							
Name	IEC_Timer_0_DB_38	**Number**	47	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

Pot2_Home [DB48]

Pot2_Home Properties							
General							
Name	Pot2_Home	**Number**	48	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Home				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Reference point position of axis
Mode	Int	0	False	True	True	True	False		Homing mode
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
ReferenceMarkPosition	Real	0.0	False	True	True	True	False		Position at which the technology object was homed
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot2_relative [DB49]

Pot2_relative Properties							
General							
Name	Pot2_relative	**Number**	49	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvRel				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Positionin-gAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Distance	Real	0.0	False	True	True	True	False		Traversing path of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot2_Reset [DB50]

Pot2_Reset Properties							
General							
Name	Pot2_Reset	**Number**	50	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Reset				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Restart	Bool	false	False	True	True	True	False		Execute axis restart
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot3_Power [DB51]

Pot3_Power Properties							
General							
Name	Pot3_Power	**Number**	51	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Power				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Enable	Bool	false	False	True	True	True	False		Enable axis
StartMode	Int	1	False	True	True	True	False		Start mode on enabling of axis
StopMode	Int	0	False	True	True	True	False		Stop mode when disabling axis
▼ Output									
Status	Bool	false	False	True	True	True	False		Axis is enabled
Busy	Bool	false	False	True	True	True	False		MC_Power is active
Error	Bool	false	False	True	True	True	False		Error at MC_Power or associated technology object
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot3_Home [DB52]

Pot3_Home Properties							
General							
Name	Pot3_Home	**Number**	52	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Home				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Reference point position of axis
Mode	Int	0	False	True	True	True	False		Homing mode
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
ReferenceMarkPosition	Real	0.0	False	True	True	True	False		Position at which the technology ob-ject was homed
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot3_Relative [DB53]

Pot3_Relative Properties							
General							
Name	Pot3_Relative	**Number**	53	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvRel				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_PositioningAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Distance	Real	0.0	False	True	True	True	False		Traversing path of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot3_Reset [DB54]

Pot3_Reset Properties							
General							
Name	Pot3_Reset	**Number**	54	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Reset				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Axis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Restart	Bool	false	False	True	True	True	False		Execute axis restart
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

Pot1_Absolute [DB55]

Pot1_Absolute Properties							
General							
Name	Pot1_Absolute	**Number**	55	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvAbs				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Positionin-gAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Absolute target position of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
Direction	Int	1	False	True	True	True	False		Direction specification
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

pot2_Absolute [DB56]

pot2_Absolute Properties							
General							
Name	pot2_Absolute	**Number**	56	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvAbs				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
Axis	TO_PositioningAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Absolute target position of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
Direction	Int	1	False	True	True	True	False		Direction specification
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

pot3_Absolute [DB57]

pot3_Absolute Properties							
General							
Name	pot3_Absolute	**Number**	57	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvAbs				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Axis	TO_Positionin-gAxis		False	False	False	False	False		Used technology object "Axis"
Execute	Bool	false	False	True	True	True	False		Start command
Position	Real	0.0	False	True	True	True	False		Absolute target position of axis
Velocity	Real	10.0	False	True	True	True	False		Velocity of axis
Direction	Int	1	False	True	True	True	False		Direction specification
▼ Output									
Done	Bool	false	False	True	True	True	False		Job is completed
Busy	Bool	false	False	True	True	True	False		Job is being executed
CommandAborted	Bool	false	False	True	True	True	False		Job was cancelled
Error	Bool	false	False	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	False	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	False	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	False	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_12 [DB61]

IEC_Timer_0_DB_12 Properties							
General							
Name	IEC_Timer_0_DB_12	**Number**	61	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_13 [DB62]

IEC_Timer_0_DB_13 Properties							
General							
Name	IEC_Timer_0_DB_13	**Number**	62	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

IEC_Timer_0_DB_4 [DB20]

IEC_Timer_0_DB_4 Properties							
General							
Name	IEC_Timer_0_DB_4	**Number**	20	**Type**	DB	**Language**	DB
Numbering	Automatic						
Information							
Title		**Author**	Simatic	**Comment**		**Family**	IEC
Version	1.0	**User-defined ID**	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Program blocks / System blocks / Program resources

MC_Reset [FB1108]

MC_Reset Properties							
General							
Name	MC_Reset	**Number**	1108	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Reset				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
▼ Axis	TO_Axis			False	False	False	False		Used technology object "Axis"
▼ Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
▼ Static									
▼ Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Execute	Bool	false	Non-retain	True	True	True	False		Start command
Restart	Bool	false	Non-retain	True	True	True	False		Execute axis restart
▼ Output									
Done	Bool	false	Non-retain	True	True	True	False		Job is completed
Busy	Bool	false	Non-retain	True	True	True	False		Job is being executed
Error	Bool	false	Non-retain	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Power [FB1107]

MC_Power Properties							
General							
Name	MC_Power	**Number**	1107	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Power				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Input									
Axis	TO_Axis			False	False	False	False		Used technology object "Axis"
Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
Static									
Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Enable	Bool	false	Non-retain	True	True	True	False		Enable axis
StartMode	Int	1	Non-retain	True	True	True	False		Start mode on enabling of axis
StopMode	Int	0	Non-retain	True	True	True	False		Stop mode when disabling axis
Output									
Status	Bool	false	Non-retain	True	True	True	False		Axis is enabled
Busy	Bool	false	Non-retain	True	True	True	False		MC_Power is active
Error	Bool	false	Non-retain	True	True	True	False		Error at MC_Power or associated technology object
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_MoveRelative [FB1104]

MC_MoveRelative Properties							
General							
Name	MC_MoveRelative	**Number**	1104	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvRel				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Input									
Axis	TO_PositioningAxis			False	False	False	False		Used technology object "Axis"
Base	TO_SpeedAxis			False	False	False	False		
Base	TO_Axis			False	False	False	False		
Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
Static									
Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Input									
Output									
InOut									
Static									
Input									
Output									
InOut									
Static									
Position	Real		Non-retain	False	False	False	False		Current axis position
Velocity	Real		Non-retain	False	False	False	False		Current axis velocity
ActualPosition	Real		Non-retain	False	False	False	False		Actual position of the axis
ActualVelocity	Real		Non-retain	False	False	False	False		Actual velocity of the axis
Actor	TO_Struct_Actor		Non-retain	False	False	False	False		Configuration data of drive connection
Type	DInt		Non-retain	False	False	False	False		Type of drive connection
InverseDirection	Bool		Non-retain	False	False	False	False		Invert direction signal
DirectionMode	Int		Non-retain	False	False	False	False		Permitted direction of rotation
DataAdaption	DInt		Non-retain	False	False	False	False		Automatic transfer of drive parameters to the CPU
PTOSliceTime	Int		Non-retain	False	False	False	False		Segment time for PTO
Interface	TO_Struct_ActorInterface		Non-retain	False	False	False	False		Configuration data of drive interface
AddressIn	VREF		Non-retain	False	False	False	False		Drive telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
AddressOut	VREF		Non-retain	False	False	False	False		Drive telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
EnableDriveOutput	VREF		Non-retain	False	False	False	False		Enable output
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
DriveReadyInput	VREF		Non-retain	False	False	False	False		Ready input
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
PTO	DWord		Non-retain	False	False	False	False		Pulse output
DriveParameter	TO_Struct_ActorDriveParameter		Non-retain	False	False	False	False		Configuration data of drive parameters
ReferenceSpeed	Real		Non-retain	False	False	False	False		Enter reference speed of drive
MaxSpeed	Real		Non-retain	False	False	False	False		Enter maximum drive speed
PulsesPerDriveRevolution	DInt		Non-retain	False	False	False	False		Pulses per motor revolution
Sensor	Array[1..1] of TO_Struct_Sensor		Non-retain	False	False	False	False		Configuration data of encoder
Sensor[1]	TO_Struct_Sensor		Non-retain	False	False	False	False		Configuration data of encoder
Type	DInt		Non-retain	False	False	False	False		Encoder type (internal parameter)
InverseDirection	Bool		Non-retain	False	False	False	False		Invert rotation direction of encoder signals
System	DInt		Non-retain	False	False	False	False		Encoder system
MountingMode	DInt		Non-retain	False	False	False	False		Select encoder mounting type
DataAdaption	DInt		Non-retain	False	False	False	False		Automatic transfer of encoder parameters to the CPU
Interface	TO_Struct_SensorInterface		Non-retain	False	False	False	False		Configuration data of encoder interface
AddressIn	VREF		Non-retain	False	False	False	False		Encoder telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
AddressOut	VREF		Non-retain	False	False	False	False		Encoder telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
Type	DInt		Non-retain	False	False	False	False		Encoder connection (internal parameter)
HSC	DWord		Non-retain	False	False	False	False		High speed counter
Number	UDInt		Non-retain	False	False	False	False		Encoder number
Parameter	TO_Struct_SensorParameter		Non-retain	False	False	False	False		Configuration data of encoder
Resolution	Real		Non-retain	False	False	False	False		Distance between two increments
StepsPerRevolution	UDInt		Non-retain	False	False	False	False		Number of encoder steps per revolution
FineResolutionXist1	UDInt		Non-retain	False	False	False	False		Number of bits for fine resolution in incremental actual value (Gn_XIST1)
FineResolutionXist2	UDInt		Non-retain	False	False	False	False		Bits in abs. actual value (GN_XIST2)
DeterminableRevolutions	UDInt		Non-retain	False	False	False	False		Number of encoder steps per revolution
DistancePerRevolution	Real		Non-retain	False	False	False	False		Load revolutions per number of motor revolutions
BehaviourGx_XIST1	DInt		Non-retain	False	False	False	False		Evaluation of the bits Gx_XIST1
ActiveHoming	TO_Struct_SensorActiveHoming		Non-retain	False	False	False	False		Configuration data for active homing
Mode	DInt		Non-retain	False	False	False	False		Active homing mode
SideInput	Bool		Non-retain	False	False	False	False		Side of reference point switch to which homing is executed with "active homing"
DigitalInputAddress	VREF		Non-retain	False	False	False	False		Input address of homing switch
RID	DWord		Non-retain	False	False	False	False		

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
HomePositionOffset	Real		Non-retain	False	False	False	False		Home position offset
SwitchLevel	Bool		Non-retain	False	False	False	False		Selection of signal level pending with approached homing switch at the CPU input
▼ PassiveHoming	TO_Struct_SensorPassiveHoming		Non-retain	False	False	False	False		Configuration data for passive homing
Mode	DInt		Non-retain	False	False	False	False		Passive homing mode
SideInput	Bool		Non-retain	False	False	False	False		Side of reference point switch to which homing is executed with "passive homing"
▼ DigitalInputAddress	VREF		Non-retain	False	False	False	False		Input address of homing switch
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
SwitchLevel	Bool		Non-retain	False	False	False	False		Selection of signal level pending with approached homing switch at the CPU input
▼ Units	TO_Struct_Units		Non-retain	False	False	False	False		Unit of measurement configuration data
LengthUnit	Int		Non-retain	False	False	False	False		Unit of measurement of parameters
▼ Mechanics	TO_Struct_Mechanics		Non-retain	False	False	False	False		Configuration data of mechanics
LeadScrew	Real		Non-retain	False	False	False	False		Distance per motor revolution
▼ DynamicLimits	TO_Struct_DynamicLimits		Non-retain	False	False	False	False		Configuration data of velocity limits
MaxVelocity	Real		Non-retain	False	False	False	False		Maximum velocity of axis
MinVelocity	Real		Non-retain	False	False	False	False		Start / stop velocity of axis
▼ DynamicDefaults	TO_Struct_DynamicDefaults		Non-retain	False	False	False	False		Configuration data of dynamic settings
Acceleration	Real		Non-retain	False	False	False	False		Acceleration of axis
Deceleration	Real		Non-retain	False	False	False	False		Deceleration of axis
EmergencyDeceleration	Real		Non-retain	False	False	False	False		Emergency stop deceleration of axis
Jerk	Real		Non-retain	False	False	False	False		Jerk of axis
▼ Modulo	TO_Struct_Modulo		Non-retain	False	False	False	False		Configuration data
Enable	Bool		Non-retain	False	False	False	False		Enable modulo property of axis
StartValue	Real		Non-retain	False	False	False	False		Define start value of modulo area
Length	Real		Non-retain	False	False	False	False		Define length of modulo area
▼ PositionLimits_SW	TO_Struct_PositionLimitsSW		Non-retain	False	False	False	False		Configuration data of software limit switches
Active	Bool		Non-retain	False	False	False	False		Enable software limit switches
MinPosition	Real		Non-retain	False	False	False	False		Position of lower software limit switch
MaxPosition	Real		Non-retain	False	False	False	False		Position of upper software limit switch
▼ PositionLimits_HW	TO_Struct_PositionLimitsHW		Non-retain	False	False	False	False		Configuration data of hardware limit switches
Active	Bool		Non-retain	False	False	False	False		Enable hardware limit switches
MinSwitchLevel	Bool		Non-retain	False	False	False	False		Voltage level at which the lower hardware limit switch reports "approach"
▼ MinSwitchAddress	VREF		Non-retain	False	False	False	False		Input address of lower hardware limit switch
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
MaxSwitchLevel	Bool		Non-retain	False	False	False	False		Voltage level at which the upper hardware limit switch reports "approach"
▼ MaxSwitchAddress	VREF		Non-retain	False	False	False	False		Input address of upper hardware limit switch
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
Homing	TO_Struct_Homing		Non-retain	False	False	False	False		Configuration data for homing
AutoReversal	Bool		Non-retain	False	False	False	False		Enable direction reversal on the hardware limit switch
ApproachDirection	Bool		Non-retain	False	False	False	False		Direction of approach and homing direction of axis
ApproachVelocity	Real		Non-retain	False	False	False	False		Approach velocity of axis
ReferencingVelocity	Real		Non-retain	False	False	False	False		Homing velocity of axis
PositionControl	TO_Struct_PositionControl		Non-retain	False	False	False	False		Configuration data
Kv	Real		Non-retain	False	False	False	False		Gain Kv of position control loop
Kpc	Real		Non-retain	False	False	False	False		Precontrol of position control loop
FollowingError	TO_Struct_FollowingError		Non-retain	False	False	False	False		Configuration data
EnableMonitoring	Bool		Non-retain	False	False	False	False		Enable following error monitoring
MinValue	Real		Non-retain	False	False	False	False		Permitted following error for small velocities
MaxValue	Real		Non-retain	False	False	False	False		Following error for maximum velocity
MinVelocity	Real		Non-retain	False	False	False	False		Velocity as of which the following error is to be adapted dynamically
PositioningMonitoring	TO_Struct_PositioningMonitoring		Non-retain	False	False	False	False		Configuration data
ToleranceTime	Real		Non-retain	False	False	False	False		Tolerance time in which the current position value must reach the positioning window
MinDwellTime	Real		Non-retain	False	False	False	False		Minimum dwell time in positioning window
Window	Real		Non-retain	False	False	False	False		Size of the window in which the current value must be located
StandstillSignal	TO_Struct_StandstillSignal		Non-retain	False	False	False	False		Configuration data
VelocityThreshold	Real		Non-retain	False	False	False	False		Size of the standstill window
MinDwellTime	Real		Non-retain	False	False	False	False		Minimum dwell time in standstill window
Simulation	TO_Struct_Simulation		Non-retain	False	False	False	False		Configuration data
Mode	UDInt		Non-retain	False	False	False	False		Simulation mode
StatusPositioning	TO_Struct_StatusPositioning		Non-retain	False	False	False	False		Current positioning status
Distance	Real		Non-retain	False	False	False	False		Current distance of axis to target position
TargetPosition	Real		Non-retain	False	False	False	False		Target position of axis
FollowingError	Real		Non-retain	False	False	False	False		Current axis following error
StatusDrive	TO_Struct_StatusDrive		Non-retain	False	False	False	False		Status of drive
InOperation	Bool		Non-retain	False	False	False	False		Operational status of the drive
CommunicationOK	Bool		Non-retain	False	False	False	False		Cyclic BUS communication between controller and drive
AdaptionState	DInt		Non-retain	False	False	False	False		Transfer status of the drive
StatusSensor	Array[1..1] of TO_Struct_StatusSensor		Non-retain	False	False	False	False		Status of encoder
StatusSensor[1]	TO_Struct_StatusSensor		Non-retain	False	False	False	False		Status of encoder
State	DInt		Non-retain	False	False	False	False		Status of the encoder value
CommunicationOK	Bool		Non-retain	False	False	False	False		Cyclic BUS communication between controller and encoder
AbsEncoderOffset	Real		Non-retain	False	False	False	False		Home position offset for value of an absolute value encoder
AdaptionState	DInt		Non-retain	False	False	False	False		Tranfer status of the encoder
StatusBits	TO_Struct_StatusBits		Non-retain	False	False	False	False		Status information of axis
Activated	Bool		Non-retain	False	False	False	False		Axis is activated
Enable	Bool		Non-retain	False	False	False	False		Axis is enabled
AxisSimulation	Bool		Non-retain	False	False	False	False		Simulation activated
NonPositionControlled	Bool		Non-retain	False	False	False	False		Position control deactivated
HomingDone	Bool		Non-retain	False	False	False	False		Axis is homed

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Done	Bool		Non-retain	False	False	False	False		No Motion Control job is active on the axis
Error	Bool		Non-retain	False	False	False	False		An error has occurred on the axis
Standstill	Bool		Non-retain	False	False	False	False		Axis is at a standstill
PositioningCommand	Bool		Non-retain	False	False	False	False		Axis executes a positioning job
VelocityCommand	Bool		Non-retain	False	False	False	False		Axis executes a job with velocity specification
HomingCommand	Bool		Non-retain	False	False	False	False		Axis executes a homing job
CommandTableActive	Bool		Non-retain	False	False	False	False		Command table is being processed
ConstantVelocity	Bool		Non-retain	False	False	False	False		Axis traverses with a constant velocity
Accelerating	Bool		Non-retain	False	False	False	False		Axis is accelerating
Decelerating	Bool		Non-retain	False	False	False	False		Axis is decelerating
ControlPanelActive	Bool		Non-retain	False	False	False	False		"Manual control" mode was enabled in the axis control panel
DriveReady	Bool		Non-retain	False	False	False	False		Drive is ready
RestartRequired	Bool		Non-retain	False	False	False	False		Restart required
SWLimitMinActive	Bool		Non-retain	False	False	False	False		Status of lower software limit switch
SWLimitMaxActive	Bool		Non-retain	False	False	False	False		Status of upper software limit switch
HWLimitMinActive	Bool		Non-retain	False	False	False	False		Status of lower hardware limit switch
HWLimitMaxActive	Bool		Non-retain	False	False	False	False		Status of upper hardware limit switch
▼ ErrorBits	TO_Struct_ErrorBits		Non-retain	False	False	False	False		Error information of axis
SystemFault	Bool		Non-retain	False	False	False	False		Internal system error
ConfigFault	Bool		Non-retain	False	False	False	False		Faulty configuration of axis
DriveFault	Bool		Non-retain	False	False	False	False		Drive has displayed an error due to failure of drive-ready signal
SWLimit	Bool		Non-retain	False	False	False	False		Software limit switch approached or overtraveled
HWLimit	Bool		Non-retain	False	False	False	False		Hardware limit switch approached or overtraveled
DirectionFault	Bool		Non-retain	False	False	False	False		Invalid movement direction
HWUsed	Bool		Non-retain	False	False	False	False		Another axis is using the same PTO (Pulse Train Output) and is enabled
SensorFault	Bool		Non-retain	False	False	False	False		Error in encoder system
CommunicationFault	Bool		Non-retain	False	False	False	False		Communication with a connected device is faulty
FollowingError	Bool		Non-retain	False	False	False	False		The maximum permitted following error has been exceeded
PositioningFault	Bool		Non-retain	False	False	False	False		The positioning axis was not positioned correctly at the end of a positioning motion
AdaptionError	Bool		Non-retain	False	False	False	False		The transfer of the drive or encoder parameters failed
▼ ControlPanel	TO_Struct_ControlPanel		Non-retain	False	False	False	False		Parameters of axis control table
▼ Input	TO_Struct_ControlPanelInput		Non-retain	False	False	False	False		Input parameters of axis control panel
TimeOut	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
EsLifeSign	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command	Array[1..1] of TO_Struct_ControlPanelInputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command[1]	TO_Struct_ControlPanelInputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
ReqCounter	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
Position	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Velocity	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Acceleration	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Jerk	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Param	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Output	TO_Struct_ControlPanelOutput		Non-retain	False	False	False	False		Output parameters of axis control panel
RTLifeSign	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command	Array[1..1] of TO_Struct_ControlPanelOutputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command[1]	TO_Struct_ControlPanelOutputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
AckCounter	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
ErrorID	Word		Non-retain	False	False	False	False		Internal parameter; please do not change!
ErrorInfo	Word		Non-retain	False	False	False	False		Internal parameter; please do not change!
Done	Bool		Non-retain	False	False	False	False		Internal parameter; please do not change!
Aborted	Bool		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal	Array[1..4] of TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
▼ Internal[1]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal[2]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal[3]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal[4]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Execute	Bool	false	Non-retain	True	True	True	False		Start command
Distance	Real	0.0	Non-retain	True	True	True	False		Traversing path of axis
Velocity	Real	10.0	Non-retain	True	True	True	False		Velocity of axis
▼ Output									
Done	Bool	false	Non-retain	True	True	True	False		Job is completed
Busy	Bool	false	Non-retain	True	True	True	False		Job is being executed
CommandAborted	Bool	false	Non-retain	True	True	True	False		Job was cancelled
Error	Bool	false	Non-retain	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_MoveJog [FB1103]

MC_MoveJog Properties							
General							
Name	MC_MoveJog	**Number**	1103	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvJog				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Input									
Axis	TO_SpeedAxis			False	False	False	False		Used technology object "Axis"
Base	TO_Axis			False	False	False	False		
Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
Static									
Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Input									
Output									
InOut									
Static									
JogForward	Bool	false	Non-retain	True	True	True	False		Jogging in positive direction
JogBackward	Bool	false	Non-retain	True	True	True	False		Jogging in negative direction
Velocity	Real	10.0	Non-retain	True	True	True	False		Target velocity of axis
PositionControlled	Bool	true	Non-retain	True	True	True	False		Position-controlled mode
Output									
InVelocity	Bool	false	Non-retain	True	True	True	False		Target velocity of axis was reached
Busy	Bool	false	Non-retain	True	True	True	False		Job is being executed
CommandAborted	Bool	false	Non-retain	True	True	True	False		Job was cancelled
Error	Bool	false	Non-retain	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_MoveAbsolute [FB1102]

MC_MoveAbsolute Properties							
General							
Name	MC_MoveAbsolute	**Number**	1102	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_MvAbs				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Input									
Axis	TO_PositioningAxis			False	False	False	False		Used technology object "Axis"
Base	TO_SpeedAxis			False	False	False	False		
Base	TO_Axis			False	False	False	False		
Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
Static									
Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Input									
Output									
InOut									
Static									
Input									
Output									
InOut									
Static									
Position	Real		Non-retain	False	False	False	False		Current axis position
Velocity	Real		Non-retain	False	False	False	False		Current axis velocity
ActualPosition	Real		Non-retain	False	False	False	False		Actual position of the axis
ActualVelocity	Real		Non-retain	False	False	False	False		Actual velocity of the axis
Actor	TO_Struct_Actor		Non-retain	False	False	False	False		Configuration data of drive connection
Type	DInt		Non-retain	False	False	False	False		Type of drive connection
InverseDirection	Bool		Non-retain	False	False	False	False		Invert direction signal
DirectionMode	Int		Non-retain	False	False	False	False		Permitted direction of rotation
DataAdaption	DInt		Non-retain	False	False	False	False		Automatic transfer of drive parameters to the CPU
PTOSliceTime	Int		Non-retain	False	False	False	False		Segment time for PTO
Interface	TO_Struct_ActorInterface		Non-retain	False	False	False	False		Configuration data of drive interface
AddressIn	VREF		Non-retain	False	False	False	False		Drive telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
AddressOut	VREF		Non-retain	False	False	False	False		Drive telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
EnableDriveOutput	VREF		Non-retain	False	False	False	False		Enable output
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
DriveReadyInput	VREF		Non-retain	False	False	False	False		Ready input
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
PTO	DWord		Non-retain	False	False	False	False		Pulse output
DriveParameter	TO_Struct_ActorDriveParameter		Non-retain	False	False	False	False		Configuration data of drive parameters
ReferenceSpeed	Real		Non-retain	False	False	False	False		Enter reference speed of drive
MaxSpeed	Real		Non-retain	False	False	False	False		Enter maximum drive speed
PulsesPerDriveRevolution	DInt		Non-retain	False	False	False	False		Pulses per motor revolution
Sensor	Array[1..1] of TO_Struct_Sensor		Non-retain	False	False	False	False		Configuration data of encoder
Sensor[1]	TO_Struct_Sensor		Non-retain	False	False	False	False		Configuration data of encoder
Type	DInt		Non-retain	False	False	False	False		Encoder type (internal parameter)
InverseDirection	Bool		Non-retain	False	False	False	False		Invert rotation direction of encoder signals
System	DInt		Non-retain	False	False	False	False		Encoder system
MountingMode	DInt		Non-retain	False	False	False	False		Select encoder mounting type
DataAdaption	DInt		Non-retain	False	False	False	False		Automatic transfer of encoder parameters to the CPU
Interface	TO_Struct_SensorInterface		Non-retain	False	False	False	False		Configuration data of encoder interface
AddressIn	VREF		Non-retain	False	False	False	False		Encoder telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
AddressOut	VREF		Non-retain	False	False	False	False		Encoder telegram (internal parameter)
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
Type	DInt		Non-retain	False	False	False	False		Encoder connection (internal parameter)
HSC	DWord		Non-retain	False	False	False	False		High speed counter
Number	UDInt		Non-retain	False	False	False	False		Encoder number
Parameter	TO_Struct_SensorParameter		Non-retain	False	False	False	False		Configuration data of encoder
Resolution	Real		Non-retain	False	False	False	False		Distance between two increments
StepsPerRevolution	UDInt		Non-retain	False	False	False	False		Number of encoder steps per revolution
FineResolutionXist1	UDInt		Non-retain	False	False	False	False		Number of bits for fine resolution in incremental actual value (Gn_XIST1)
FineResolutionXist2	UDInt		Non-retain	False	False	False	False		Bits in abs. actual value (GN_XIST2)
DeterminableRevolutions	UDInt		Non-retain	False	False	False	False		Number of encoder steps per revolution
DistancePerRevolution	Real		Non-retain	False	False	False	False		Load revolutions per number of motor revolutions
BehaviourGx_XIST1	DInt		Non-retain	False	False	False	False		Evaluation of the bits Gx_XIST1
ActiveHoming	TO_Struct_SensorActiveHoming		Non-retain	False	False	False	False		Configuration data for active homing
Mode	DInt		Non-retain	False	False	False	False		Active homing mode
SideInput	Bool		Non-retain	False	False	False	False		Side of reference point switch to which homing is executed with "active homing"
DigitalInputAddress	VREF		Non-retain	False	False	False	False		Input address of homing switch
RID	DWord		Non-retain	False	False	False	False		

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
HomePositionOffset	Real		Non-retain	False	False	False	False		Home position offset
SwitchLevel	Bool		Non-retain	False	False	False	False		Selection of signal level pending with approached homing switch at the CPU input
▼ PassiveHoming	TO_Struct_SensorPassiveHoming		Non-retain	False	False	False	False		Configuration data for passive homing
Mode	DInt		Non-retain	False	False	False	False		Passive homing mode
SideInput	Bool		Non-retain	False	False	False	False		Side of reference point switch to which homing is executed with "passive homing"
▼ DigitalInputAddress	VREF		Non-retain	False	False	False	False		Input address of homing switch
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
SwitchLevel	Bool		Non-retain	False	False	False	False		Selection of signal level pending with approached homing switch at the CPU input
▼ Units	TO_Struct_Units		Non-retain	False	False	False	False		Unit of measurement configuration data
LengthUnit	Int		Non-retain	False	False	False	False		Unit of measurement of parameters
▼ Mechanics	TO_Struct_Mechanics		Non-retain	False	False	False	False		Configuration data of mechanics
LeadScrew	Real		Non-retain	False	False	False	False		Distance per motor revolution
▼ DynamicLimits	TO_Struct_DynamicLimits		Non-retain	False	False	False	False		Configuration data of velocity limits
MaxVelocity	Real		Non-retain	False	False	False	False		Maximum velocity of axis
MinVelocity	Real		Non-retain	False	False	False	False		Start / stop velocity of axis
▼ DynamicDefaults	TO_Struct_DynamicDefaults		Non-retain	False	False	False	False		Configuration data of dynamic settings
Acceleration	Real		Non-retain	False	False	False	False		Acceleration of axis
Deceleration	Real		Non-retain	False	False	False	False		Deceleration of axis
EmergencyDeceleration	Real		Non-retain	False	False	False	False		Emergency stop deceleration of axis
Jerk	Real		Non-retain	False	False	False	False		Jerk of axis
▼ Modulo	TO_Struct_Modulo		Non-retain	False	False	False	False		Configuration data
Enable	Bool		Non-retain	False	False	False	False		Enable modulo property of axis
StartValue	Real		Non-retain	False	False	False	False		Define start value of modulo area
Length	Real		Non-retain	False	False	False	False		Define length of modulo area
▼ PositionLimits_SW	TO_Struct_PositionLimitsSW		Non-retain	False	False	False	False		Configuration data of software limit switches
Active	Bool		Non-retain	False	False	False	False		Enable software limit switches
MinPosition	Real		Non-retain	False	False	False	False		Position of lower software limit switch
MaxPosition	Real		Non-retain	False	False	False	False		Position of upper software limit switch
▼ PositionLimits_HW	TO_Struct_PositionLimitsHW		Non-retain	False	False	False	False		Configuration data of hardware limit switches
Active	Bool		Non-retain	False	False	False	False		Enable hardware limit switches
MinSwitchLevel	Bool		Non-retain	False	False	False	False		Voltage level at which the lower hardware limit switch reports "approach"
▼ MinSwitchAddress	VREF		Non-retain	False	False	False	False		Input address of lower hardware limit switch
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
MaxSwitchLevel	Bool		Non-retain	False	False	False	False		Voltage level at which the upper hardware limit switch reports "approach"
▼ MaxSwitchAddress	VREF		Non-retain	False	False	False	False		Input address of upper hardware limit switch
RID	DWord		Non-retain	False	False	False	False		
AREA	Byte		Non-retain	False	False	False	False		

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
DB_NUMBER	UInt		Non-retain	False	False	False	False		
OFFSET	UDInt		Non-retain	False	False	False	False		
Homing	TO_Struct_Homing		Non-retain	False	False	False	False		Configuration data for homing
AutoReversal	Bool		Non-retain	False	False	False	False		Enable direction reversal on the hardware limit switch
ApproachDirection	Bool		Non-retain	False	False	False	False		Direction of approach and homing direction of axis
ApproachVelocity	Real		Non-retain	False	False	False	False		Approach velocity of axis
ReferencingVelocity	Real		Non-retain	False	False	False	False		Homing velocity of axis
PositionControl	TO_Struct_PositionControl		Non-retain	False	False	False	False		Configuration data
Kv	Real		Non-retain	False	False	False	False		Gain Kv of position control loop
Kpc	Real		Non-retain	False	False	False	False		Precontrol of position control loop
FollowingError	TO_Struct_FollowingError		Non-retain	False	False	False	False		Configuration data
EnableMonitoring	Bool		Non-retain	False	False	False	False		Enable following error monitoring
MinValue	Real		Non-retain	False	False	False	False		Permitted following error for small velocities
MaxValue	Real		Non-retain	False	False	False	False		Following error for maximum velocity
MinVelocity	Real		Non-retain	False	False	False	False		Velocity as of which the following error is to be adapted dynamically
PositioningMonitoring	TO_Struct_PositioningMonitoring		Non-retain	False	False	False	False		Configuration data
ToleranceTime	Real		Non-retain	False	False	False	False		Tolerance time in which the current position value must reach the positioning window
MinDwellTime	Real		Non-retain	False	False	False	False		Minimum dwell time in positioning window
Window	Real		Non-retain	False	False	False	False		Size of the window in which the current value must be located
StandstillSignal	TO_Struct_StandstillSignal		Non-retain	False	False	False	False		Configuration data
VelocityThreshold	Real		Non-retain	False	False	False	False		Size of the standstill window
MinDwellTime	Real		Non-retain	False	False	False	False		Minimum dwell time in standstill window
Simulation	TO_Struct_Simulation		Non-retain	False	False	False	False		Configuration data
Mode	UDInt		Non-retain	False	False	False	False		Simulation mode
StatusPositioning	TO_Struct_StatusPositioning		Non-retain	False	False	False	False		Current positioning status
Distance	Real		Non-retain	False	False	False	False		Current distance of axis to target position
TargetPosition	Real		Non-retain	False	False	False	False		Target position of axis
FollowingError	Real		Non-retain	False	False	False	False		Current axis following error
StatusDrive	TO_Struct_StatusDrive		Non-retain	False	False	False	False		Status of drive
InOperation	Bool		Non-retain	False	False	False	False		Operational status of the drive
CommunicationOK	Bool		Non-retain	False	False	False	False		Cyclic BUS communication between controller and drive
AdaptionState	DInt		Non-retain	False	False	False	False		Transfer status of the drive
StatusSensor	Array[1..1] of TO_Struct_StatusSensor		Non-retain	False	False	False	False		Status of encoder
StatusSensor[1]	TO_Struct_StatusSensor		Non-retain	False	False	False	False		Status of encoder
State	DInt		Non-retain	False	False	False	False		Status of the encoder value
CommunicationOK	Bool		Non-retain	False	False	False	False		Cyclic BUS communication between controller and encoder
AbsEncoderOffset	Real		Non-retain	False	False	False	False		Home position offset for value of an absolute value encoder
AdaptionState	DInt		Non-retain	False	False	False	False		Tranfer status of the encoder
StatusBits	TO_Struct_StatusBits		Non-retain	False	False	False	False		Status information of axis
Activated	Bool		Non-retain	False	False	False	False		Axis is activated
Enable	Bool		Non-retain	False	False	False	False		Axis is enabled
AxisSimulation	Bool		Non-retain	False	False	False	False		Simulation activated
NonPositionControlled	Bool		Non-retain	False	False	False	False		Position control deactivated
HomingDone	Bool		Non-retain	False	False	False	False		Axis is homed

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Done	Bool		Non-retain	False	False	False	False		No Motion Control job is active on the axis
Error	Bool		Non-retain	False	False	False	False		An error has occurred on the axis
Standstill	Bool		Non-retain	False	False	False	False		Axis is at a standstill
PositioningCommand	Bool		Non-retain	False	False	False	False		Axis executes a positioning job
VelocityCommand	Bool		Non-retain	False	False	False	False		Axis executes a job with velocity specification
HomingCommand	Bool		Non-retain	False	False	False	False		Axis executes a homing job
CommandTableActive	Bool		Non-retain	False	False	False	False		Command table is being processed
ConstantVelocity	Bool		Non-retain	False	False	False	False		Axis traverses with a constant velocity
Accelerating	Bool		Non-retain	False	False	False	False		Axis is accelerating
Decelerating	Bool		Non-retain	False	False	False	False		Axis is decelerating
ControlPanelActive	Bool		Non-retain	False	False	False	False		"Manual control" mode was enabled in the axis control panel
DriveReady	Bool		Non-retain	False	False	False	False		Drive is ready
RestartRequired	Bool		Non-retain	False	False	False	False		Restart required
SWLimitMinActive	Bool		Non-retain	False	False	False	False		Status of lower software limit switch
SWLimitMaxActive	Bool		Non-retain	False	False	False	False		Status of upper software limit switch
HWLimitMinActive	Bool		Non-retain	False	False	False	False		Status of lower hardware limit switch
HWLimitMaxActive	Bool		Non-retain	False	False	False	False		Status of upper hardware limit switch
▼ ErrorBits	TO_Struct_ErrorBits		Non-retain	False	False	False	False		Error information of axis
SystemFault	Bool		Non-retain	False	False	False	False		Internal system error
ConfigFault	Bool		Non-retain	False	False	False	False		Faulty configuration of axis
DriveFault	Bool		Non-retain	False	False	False	False		Drive has displayed an error due to failure of drive-ready signal
SWLimit	Bool		Non-retain	False	False	False	False		Software limit switch approached or overtraveled
HWLimit	Bool		Non-retain	False	False	False	False		Hardware limit switch approached or overtraveled
DirectionFault	Bool		Non-retain	False	False	False	False		Invalid movement direction
HWUsed	Bool		Non-retain	False	False	False	False		Another axis is using the same PTO (Pulse Train Output) and is enabled
SensorFault	Bool		Non-retain	False	False	False	False		Error in encoder system
CommunicationFault	Bool		Non-retain	False	False	False	False		Communication with a connected device is faulty
FollowingError	Bool		Non-retain	False	False	False	False		The maximum permitted following error has been exceeded
PositioningFault	Bool		Non-retain	False	False	False	False		The positioning axis was not positioned correctly at the end of a positioning motion
AdaptionError	Bool		Non-retain	False	False	False	False		The transfer of the drive or encoder parameters failed
▼ ControlPanel	TO_Struct_ControlPanel		Non-retain	False	False	False	False		Parameters of axis control table
▼ Input	TO_Struct_ControlPanelInput		Non-retain	False	False	False	False		Input parameters of axis control panel
TimeOut	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
EsLifeSign	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command	Array[1..1] of TO_Struct_ControlPanelInputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command[1]	TO_Struct_ControlPanelInputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
ReqCounter	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
Position	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Velocity	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Acceleration	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Jerk	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
Param	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Output	TO_Struct_ControlPanelOutput		Non-retain	False	False	False	False		Output parameters of axis control panel
RTLifeSign	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command	Array[1..1] of TO_Struct_ControlPanelOutputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Command[1]	TO_Struct_ControlPanelOutputCmd		Non-retain	False	False	False	False		Internal parameter; please do not change!
AckCounter	DInt		Non-retain	False	False	False	False		Internal parameter; please do not change!
ErrorID	Word		Non-retain	False	False	False	False		Internal parameter; please do not change!
ErrorInfo	Word		Non-retain	False	False	False	False		Internal parameter; please do not change!
Done	Bool		Non-retain	False	False	False	False		Internal parameter; please do not change!
Aborted	Bool		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal	Array[1..4] of TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
▼ Internal[1]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal[2]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal[3]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
▼ Internal[4]	TO_Struct_Internal		Non-retain	False	False	False	False		Parameters for internal use
Id	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Value	Real		Non-retain	False	False	False	False		Internal parameter; please do not change!
Execute	Bool	false	Non-retain	True	True	True	False		Start command
Position	Real	0.0	Non-retain	True	True	True	False		Absolute target position of axis
Velocity	Real	10.0	Non-retain	True	True	True	False		Velocity of axis
Direction	Int	1	Non-retain	True	True	True	False		Direction specification
▼ Output									
Done	Bool	false	Non-retain	True	True	True	False		Job is completed
Busy	Bool	false	Non-retain	True	True	True	False		Job is being executed
CommandAborted	Bool	false	Non-retain	True	True	True	False		Job was cancelled
Error	Bool	false	Non-retain	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Home [FB1101]

MC_Home Properties							
General							
Name	MC_Home	**Number**	1101	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Home				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
▼ Axis	TO_Axis			False	False	False	False		Used technology object "Axis"
▼ Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
▼ Static									
▼ Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Execute	Bool	false	Non-retain	True	True	True	False		Start command
Position	Real	0.0	Non-retain	True	True	True	False		Reference point position of axis
Mode	Int	0	Non-retain	True	True	True	False		Homing mode
▼ Output									
Done	Bool	false	Non-retain	True	True	True	False		Job is completed
Busy	Bool	false	Non-retain	True	True	True	False		Job is being executed
CommandAborted	Bool	false	Non-retain	True	True	True	False		Job was cancelled
Error	Bool	false	Non-retain	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
ReferenceMarkPosition	Real	0.0	Non-retain	True	True	True	False		Position at which the technology object was homed
InOut									
▼ Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!

Program blocks / System blocks / Program resources

MC_Halt [FB1100]

MC_Halt Properties							
General							
Name	MC_Halt	**Number**	1100	**Type**	FB	**Language**	SCL
Numbering	Automatic						
Information							
Title		**Author**	SIMATIC	**Comment**		**Family**	BasicMC
Version	8.0	**User-defined ID**	MC_Halt				

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engineering	Setpoint	Supervision	Comment
▼ Input									
▼ Axis	TO_SpeedAxis			False	False	False	False		Used technology object "Axis"
▼ Base	TO_Axis			False	False	False	False		
▼ Base	TO_AnyMotionObject			False	False	False	False		
Input									
Output									
InOut									
▼ Static									
▼ Header	TO_Struct_Header		Non-retain	False	False	False	False		Version information of technology object
VersionMaj	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
VersionMin	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Type	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved1	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Reserved2	Int		Non-retain	False	False	False	False		Internal parameter; please do not change!
Input									
Output									
InOut									
Static									
Input									
Output									
InOut									
Static									
Execute	Bool	false	Non-retain	True	True	True	False		Start command
▼ Output									
Done	Bool	false	Non-retain	True	True	True	False		Job is completed
Busy	Bool	false	Non-retain	True	True	True	False		Job is being executed
CommandAborted	Bool	false	Non-retain	True	True	True	False		Job was cancelled
Error	Bool	false	Non-retain	True	True	True	False		Error during execution of the job
ErrorID	Word	16#0	Non-retain	True	True	True	False		Error ID for parameter "Error"
ErrorInfo	Word	16#0	Non-retain	True	True	True	False		Error info ID for parameter "ErrorID"
InOut									
▼ Static									
FB_ID	DInt	0	Non-retain	False	False	False	False		Internal parameter; please do not change!