SOP – Create and Configure Azure Blob Storage Account

1. Objective

The objective of this task is to create an Azure Storage Account and configure its basic settings, security, networking, redundancy, and storage endpoints.


2. Prerequisites

- An active Microsoft Azure subscription.
- Access to the Azure Portal.
- Permission to create resource groups and storage accounts.

3. Procedure


Step 1: Open Azure Blob Storage

1. Sign in to the Microsoft Azure Portal.
2. Navigate to **Storage Center → Blob Storage**.
3. Check the list of existing storage accounts.
4. Click **Create** to start creating a new storage account.




Step 2: Configure Basic Settings

1. Select the Azure subscription.
2. Create a new resource group named `rg-mayank`.
3. Enter the storage account name as `mayankstorage101`.
4. Select the region as **Central India**.
5. Select the primary service as **Azure Blob Storage or Azure Data Lake Storage**.
6. Choose **Standard** performance.
7. Select **Locally Redundant Storage (LRS)** as the redundancy option.
8. Click **Next** to continue.




Step 3: Configure Advanced Settings

1. Open the **Advanced** tab.
2. Keep Hierarchical Namespace disabled for a standard Blob Storage configuration.
3. Keep SFTP and NFS v3 disabled.
4. Keep cross-tenant replication disabled.
5. Select the **Hot** access tier for frequently accessed data.
6. Click **Next**.




Step 4: Configure Networking

1. Open the **Networking** tab.
2. Select **Enable** for public network access.
3. Select **Enable from all networks** as the public network access scope.
4. Leave the private endpoint unconfigured for this basic setup.
5. Click **Next**.




Step 5: Configure Security

1. Open the **Security** tab.
2. Enable **Require secure transfer for REST API operations**.
3. Keep anonymous access on individual containers disabled.
4. Keep storage account key access enabled for this lab.
5. Set the minimum TLS version to **Version 1.2**.
6. Keep the other settings at their default values.
7. Click **Next**.



Step 6: Review and Create


1. Continue through Data Protection, Encryption, Tags tabs, keeping the default settings where appropriate.
2. Open **Review + create**.
3. Verify the subscription, resource group, region, storage account name, performance, redundancy settings.
4. Click **Create** to deploy the storage account.
5. Wait for the deployment to complete successfully.



Step 7: Verify the Storage Account


1. Open the newly created storage account named `mayankstorage101`.

2. On the Overview page, verify that the provisioning state is **Succeeded**.
3. Confirm the resource group is `rg-mayank`.
4. Verify the location is Central India, performance is Standard, and redundancy is LRS.




Step 8: Verify Configuration Settings

1. Open **Settings → Configuration**.
2. Verify that anonymous Blob access is disabled.
3. Confirm storage account key access is enabled.
4. Verify the minimum TLS version is Version 1.2.
5. Confirm the default Blob access tier is Hot.




Step 9: Verify Redundancy

1. Open **Data management → Redundancy**.
2. Check that the redundancy option is **Locally redundant storage (LRS)**.
3. Verify that Central India is listed as the primary location.



Step 10: Verify Storage Endpoints

1. Open **Settings → Endpoints**.
2. Verify that the storage account endpoints are available.
3. Locate the Blob service endpoint.
4. Confirm that the Blob endpoint follows the Azure format: `https://<storage-account-name>.blob.core.windows.net/`.
5. Note that File, Queue, Table endpoints are also displayed for this general-purpose v2 storage account.



Result

The Azure Storage Account `mayankstorage101` was created successfully in the Central India region under the resource group `rg-mayank`. The account uses Standard performance, LRS redundancy, the Hot access tier, secure transfer, and TLS 1.2.