I'm not robot

reCAPTCHA

Continue

I'm not robot

reCAPTCHA

How to remove multiple pages from pdf file

How to delete multiple pages from pdf. How to remove multiple pages from pdf file. How to delete multiple pages from a pdf document.

Discard pages You can not use the online PDF tool online to remove single or more pages from the PDF document. No file size limit. Just upload, modify and save the file.Secure PDF Removeryou page You can remove pages from PDF online without worries. The loaded documents will be deleted 60 minutes after processing. No one can access your files and your privacy is guaranteed. Made for all your devices pdf pages online with any browser on Mac, Windows or Linux. No matter where or when you want to delete a page. Works for all platforms! Delete a page for FreeThe SmallPDF Delete PDF Online Tool Pages Allows you to delete a page from any point in the document and save it as a word file. Just remove what you don't need and download. Download. Easy to use our removal of the PDF page easy to use, your documents will be smaller and will only include the pages you really need. Simple, isn't it? Access from AnyWhereto Delete a page from a PDF you do not need to download or install any software. Just upload your file, delete pages from the PDF file and download it again. Today I will show me how to delete the pages in Word. Maybe you have unwanted content on some of your pages you want to get rid of you cancel all pages. Or there are some blank pages at the end of your word document you want to delete. In this post, you will learn how to remove a single page or more pages in MS Word using the methods described below. The default option to delete pages in Word is to select and delete content in pages, then Word will automatically cancine the page. Microsoft Word does not have an agreement with the pages. Rather, he takes care of the text (contained) on those pages. Therefore, there is no way where you can delete the pages in Word with a single action unless it is helpful of some VBA code that I share soon with you. In this illustration a VBA code was used to get these results. You will learn this trick in the sixth section of this post. How to select and delete pages in Word This option results in the selection of all text on the page or on the pages you want to delete, and then delete using the Delete button or the backspace. Without further ADO, you can select and delete pages in MS Word. Quick Solution: Select all the contents on the page or on the pages you want to delete. Then press Delete or Backspace to delete all the word content will automatically eliminate all the pages that kept the content. If you don't understand the simple steps above, read below for further explanations. Option 1: Using the box Ã ¢ â,¬ Å "Navigation" in MS Word, one of the simpler modes you can select and delete pages or unwanted is to use the navigation box. Allows you to view Thumbnails pages, which you can select and delete with the Delete key. Follow the steps below to learn how to: activate the navigation box. Go to tab View and place a checkmark on the navigation pane. Click to activate the the tab in the move pane. Select the page you want to delete then press DELETE. In my case, I am deleting the extra blank page (page 12) As soon as you press the delete key, the selected page will be deleted. Just know that in Word you can select and delete pages one after the other. You can't run a mass delete unless with the help of some Macros that you'll learn even later in this tutorial. Option 2: How to Select and Delete Current Page In this method, I assume you want to delete only one page in the Word document. You will learn to delete more pages in the next section. With this approach, you can easily delete only the current page. So, if you are not on the page you want to remove, navigate to that page and click inside the page. If you are already on the page you want to delete, then let's start with the following steps: Press Ctrl+G or F5. Word will display the Find and Replace dialog. Click to activate the Go to tab. In the Go To Which List box, click to select Page (It should be selected by default) In the Enter page number field, type \page. Then press Enter and close the dialog. Now every content on this page should be selected. Press Delete to delete the page. NOTE: If there were pages after the deleted page, those pages move to replace the page (s) you just deleted. Option 3: How to select and delete multiple pages Using Find and Replace, you can also select and delete multiple pages at once. This is especially useful if the pages you want to delete are many consecutive pages, such as pages 23 to 30 (7 consecutive pages). To select and delete such multiple pages in Word, the steps are as follows: Press Ctrl+G or F5. Word will display the Find and Replace dialog. Click to activate the Go to tab. In the Go to Which list box, click to select Page (it is selected by default) Type 23 in the Send Page Number field. We used 23 because this is the page we want to start deleting from. So, you can enter a different page number. It should be the top of the pages you want to delete. After typing the page number (23), press Enter. Press the Esc key to cancel the dialog. Without clicking anywhere or pressing any key, press the F8 key once. Then press Ctrl+G or F5 key again to display the Find and Replace dialog. This time around, type 30 in the field labeled "Inser page number." We're typing 30 because this is the page we want to select and delete. So, if you're deleting from page 5 to 20, you'll enter 5 for the And then 20 for the second time. After typing the page number (30), press Enter. You will notice that all the content on pages 23 to 30 is selected. Press the Esc key to close the Find and Replace dialog. At this point, if you press the Backspace or Delete key, Word will delete all 7 pages (starting from page 23 to 30). This is the way you can delete multiple pages in Word. Option 4: Select and delete pages using the mouse mouse way you can delete pages in Word is to highlight all the contents of the pages you want to delete using your mouse, then press Delete. To highlight or select an entire page with your mouse: Go to the page you want to select and place the cursor at the top of the text. Click and hold the primary mouse button (i.e. the left button). Holding down the mouse button, drag the cursor to the end of the text on the page, then let go of the mouse button. Bonus tip: If you delete more pages using the mouse to select, zoom in on the pages to say 10% or 20% so you can see more pages on the screen at the same time. Then use your mouse to select the pages you want to remove and press the delete key to delete them. Watch the screenshot: Option 5: Select text using the keyboard You can also select and delete pages in Word using the keyboard. To do this, place the cursor at the top of the page and press Ctrl+Shift+Down Arrow. Word will make the selection by paragraph after paragraph until the last paragraph. To deselect a paragraph while still pressing Ctrl+Shift, press the up arrow key. Step 2: After making the selection, press the Delete or Backspace key to delete the text. As soon as you delete the text, Word will also delete the page. However, if there are pages after the deleted page, those pages will replace the deleted pages. Option 6: How to Delete Blank Pages in Word Sometimes, you might want to delete not only the pages, but some more blank pages especially at the end of the document. Normally, this additional page is caused by a non-removable final paragraph that is pushed down into a new blank page. When this happens, deleting this page with the Delete or Backspace key will not work. Instead, you should format the final paragraph to fit the previous page. The steps below will show you how. Press Ctrl+Shift+8 on your PC or Command+8 on your Mac. This will show all the paragraph marks in the document.Select the last paragraph mark on the last empty pageChange the font size to 1 or 01 and press enter. As soon as you change the font size of the last paragraph mark, it will be placed on the previous page, removing the unwanted blank page. Again, press Ctrl+Shift+8 on the PC (or Command-Â°+8 on the Mac). This will hide all paragraph marks in the document. Option 7: Delete specific pages in Word using Macro By default, you cannot delete pages in Word with a single action; like typing the page number of the pages you want to delete, and then clicking a button, the pages will be deleted. However, with the help of some VBA code, task is possible. All you need to do is type the page numbers into a comma-separated box, then click OK to delete the specified pages. Without further ado, let's begin. With the Word document open, press Alt+F11. This shortcut will open the VB Editor Window. In the Project pane, right-click ThisDocument under the project you are working on, then go to Insert Form. A window of the module module module appear. Copy and paste the following code: Sub DeletePagesInWord () is Dim iRange as gamma is Dim iPage As String is Dim iDoc as a document of Dim iPageCount as an integer is Dim iArr is Dim I, XSplitC Count come Long is about to apply.screenupdating = false to set idoc = activedocument is about to be ipage = inputbox (â€TM) = ÃScreenUpdating = True End Sub here as the editor will paste the code above: press F5 to test the code. Here the macro has been added to the shortcut toolbar for easy access if the code works fine, save the macro and assign wdGoToAbsolute, iArr (I) Bookmarks (A \ Page A) Range.Delete Â© Ã it to a shortcut key or pin it to the shortcut toolbar. The remaining steps will show you how to enter a macro code to the QAT. Press Ctrl+S to save the macro and then close the VB.right Editor window-Click one of the tabs and select Customize the Quick Access toolbar from the shortcut menu. Select Macro from the Labelled drop-down menu Choose Commands From. Select the macro you saved and click the Add button to add it to the Quick Access toolbar. Now you will have the macro available on your QAT. This is just a daily process. Next time you want to delete pages in Word, you don't have to go through all the steps, click on the macro icon from QAT and the word prompt you for the page number of pages you want to delete. Things you should notice here: since the document contains the VBA code, make sure to save it as a macro-enabled document.Using the macro from the Quick Access toolbar only works for the Word document that contains the code. For this code works in another document, also copy and paste the code into the document. But if you want the macro to work in all your word documents, you need to consider creating an additional bonus option: Delete Current Page Using VBA Macro This is a very quick way to delete the current page in the document. Using the procedures in the previous approach to delete pages in Word, you can use the macro below to save the day: DeleteCurrentPage Sub () is ActiveDocument.Bookmarks (A \ Page A) Range.Delete End Sub You can assign this macro to a hotkey so you can easily delete the current page or Pin in QAT as shown in option 6. To assign a macro to a From keyboard read this guide. Conclusion You can use the above options to remove the pages in Word. However, if you try all the options on this page and you can still not delete some pages in the document, let me know from your comment below. under. under.