Pimlico Paymaster Client

The Pimlico paymaster actions in permissionless.js only work with the v2 Pimlico API. The v1 API for paymasters is deprecated and will be removed in the future.

This version, instead of simply signing over the passed-in User Operation, estimates the gas values for the User Operation and then signs over the estimated gas values, returning not only thepaymasterAndData but also thepreVerificationGas ,verificationGasLimit , andcallGasLimit .

A Pimlico Paymaster Client is an interface to the Pimlico-specific paymaster methods.

To create a Pimlico Paymaster Client, create a basic client and extend it with the Pimlico Paymaster Actions.

Import

import{ pimlicoPaymasterActions }from'permissionless/actions/pimlico'

Usage

Initialize a Bundler Client with your desired Chain (e.g. mainnet) and Transport (e.g. http) from viem by creating a simple client and extending it with the Pimlico paymaster methods.

import{createClient,http}from'viem' import{sepolia}from'viem/chains' import{bundlerActions,ENTRYPOINT_ADDRESS_V07}from'permissionless' import{pimlicoPaymasterActions}from'permissionless/actions/pimlico'

 $constbundler Client = create Client \{\{chain: sepolia, transport: http("https://api.pimlico.io/v2/sepolia/rpc?apikey=YOUR_API_KEY_HERE"), \}\} \\ .extend(pimlicoPaymasterActions(ENTRYPOINT_ADDRESS_V07))$

Then you can consume Pimlico Paymaster Actions:

maxFeePerGas:113001000n, maxPriorityFeePerGas:113000000n, signature:"0xf1513a8537a079a4d728bb87099b2c901e2c9034e60c95a4d41ac1ed75d6ee90270d52b48af30aa036e9a205ea008e1c62b317e7b3f88b3f302d45fb1ba76a191b" } })

Alternatively, you can initialize a Paymaster Client with thecreatePimlicoPaymasterClient method:

import{ http }from'viem' import{ sepolia }from'viem/chains' import{ ENTRYPOINT_ADDRESS_V07 }from'permissionless' import{ createPimlicoPaymasterClient }from'permissionless/clients/pimlico";

constpimlicoPaymasterClient=createPimlicoPaymasterClient({ chain: sepolia, transport:http("https://api.pimlico.io/v2/sepolia/rpc?apikey=YOUR_API_KEY_HERE"), entryPoint:ENTRYPOINT ADDRESS V07 })