Seed Phrase Module - tKey iOS SDK

SeedPhraseModule is a Swift module that provides functionality for setting, changing, getting, and deleting seed phrases for a ThresholdKey object.

To use the SeedPhraseModule in your Swift project, you will need to import the module as follows:

import tkey_pkg SeedPhraseModule is a class that provides the following methods:

Function Description Arguments Async return set_seed_phrase Set seed phrase to corresponding tKey threshold_key: ThresholdKey, format: String, phrase: String?, number_of_wallets: UInt32 Yes void change_phrase Changes specific seed phrase threshold_key: ThresholdKey, old_phrase: String, new_phrase: String Yes void get_seed_phrases Gets all seed phrases stored in tKey. threshold_key: ThresholdKey Yes [seedPhraseStruct] delete_seed_phrase Delete the seed phrase threshold_key: ThresholdKey, phrase: String Yes void

set seed phrase()

â

set_seed_phrase(threshold_key: ThresholdKey, format: String, phrase: String?, number_of_wallets: UInt32) async throws

This function sets the seed phrase for the given ThresholdKey.

Parameters<u>â</u>

Parameters Type Description threshold_key ThresholdKey The ThresholdKey object to set the seed phrase for. format String The format of the seed phrase. phrase String? The seed phrase. If nil, a random seed phrase is generated. number_of_wallets UInt32 The number of wallets to derive from the seed phrase. Returns

Void

Throws

Error: An error if the operation fails.

change_phrase()

â

change phrase(threshold key: ThresholdKey, old phrase: String, new phrase: String) async throws

This function changes the seed phrase of the given ThresholdKey. The old_phrase parameter specifies the old seed phrase, and the new_phrase parameter specifies the new seed phrase. The function is asynchronous and can throw an error.

Parametersâ

Parameters Type Description threshold_key ThresholdKey The ThresholdKey object to change the seed phrase for. old_phrase String The old seed phrase. new_phrase String The new seed phrase. Returns

Void

Throws

• Error: An error if the operation fails.

get_seed_phrases()

â

get_seed_phrases(threshold_key: ThresholdKey) throws -> [seedPhraseStruct]

This function returns an array of seedPhraseStruct objects, which contain the seed phrases and their type for the given ThresholdKey.

Parameters<u>â</u>

Parameters Type Description threshold key ThresholdKey The ThresholdKey object to get the seed phrases for. Returns

seedPhraseStruct

Throws

• Error: An error if the operation fails.

delete_seed_phrase()

<u>â</u>

delete_seed_phrase(threshold_key: ThresholdKey, phrase: String) async throws

This method deletes a seed phrase from the given ThresholdKey.

Parameters<u>â</u>

Parameters Type Description threshold_key ThresholdKey The ThresholdKey instance from which to delete the seed phrase. phrase String The seed phrase to delete, as a string. Returns

Void

Throws

• Error: An error if the operation fails. Edit this page Previous Security Question Next Share Serialization