

ERGO TOOLS

# Case Manual



---

IVAN NAIL ULLOA

MIA KING

INDEX

# Table of Content

03

Case 1: Basic Setup & First  
Prompt

09


Case 2: Project  
Management

13

Case 3: Layout View


18

Case 4: Large Project  
Navigation, Layout Review, &  
Export



## CASE 1

# Basic Setup & First Prompt



**Objective:** Create a new project, create a worker, assign worker and job information, enter analysis data, save the project, and reopen it successfully.

### Preconditions

- The software shortcut is available on the desktop.
- A folder named "Projects" exists on the desktop.
- The user has access to the default test environment.

### Steps



1. Launch the software
  - Double click **Run\_ergotools – Shortcut** on the desktop.
  - If needed, drag the top bar of the software window to center it on the screen.

## CASE 1

### 2. Create a project


- Click "Project" in the upper-left corner.
- Click "Save", or click the Save icon in the top-left toolbar.
- In the save window, select Desktop from the left panel.
- Open the "Projects" folder.
- Enter the file name **Test\_Project\_01** and click "Save"
- A pop-up window will request two inputs:
  - Name: **Test\_Project**
  - Description: *This is a testing scenario*
- Confirm the inputs

\***Expected result:** A confirmation message appears indicating that the project was saved successfully.



### 3. Create a worker

- Click the Workers Management icon (second icon from left to right in the relevant row).



- In the Workers Management window, click "New".
- Enter the Worker ID: **Worker\_01**
- Click "Save"
- Confirm that the software displays a successful save message.

## CASE 1

4. Remove the default worker entry
  - Click the button to return to Default.
  - Click "Delete"
  - Confirm the warning message.
  - Verify that **Worker\_01** now becomes the active worker
  - Click "Close".

5. Enter personal characteristics
  - Reopen the worker editing window.
  - Update the worker information as follows:
    - Date of Birth: *01/01/1980*
    - Sex: *Male*
    - Height: *72 inches*
  - Weight: *180*
  - Click "Save"
  - Close the worker management window.

**\*Expected result:** The worker record is saved with the updated demographic information.

### 6. Add job details

- On the main interface, assign the worker to the following organizational levels:
  - Plant
  - Section
  - Line
  - Station
  - Shift





RETURN

DELETE

CLOSE

## CASE 1

- For Plant:
  - Click the button next to "Plant".
  - In the Plant Management window, delete the "Default" entry first.
  - Enter:
    - Plant Name (ID): **Testing\_Plant\_01**
    - Description: *This is a testing plant*
    - Opening Date: *12/12/1970*
  - Click Save, then Close.
- For Section:
  - Open the edit window.
  - Enter **Testing\_Section\_01**
  - Click "Save", then "Close".
- For Line:
  - Open the edit window.
  - Enter **Testing\_Line\_01**
  - Click "Save", then "Close".
- For Station:
  - Open the edit window.
  - Enter **Testing\_Station\_01**
  - Click "Save", then "New"
  - Create **Testing\_Station\_02**
  - Click "Save", then "Close"
  - Return to the main interface and select **Testing\_Station\_01** as the active station.
- For Shift:
  - Open the edit window.
  - Keep the existing Shift ID.
  - Change the end time from *5:00 PM* to *4:00 PM*.
  - Click "Save," then "Close."



## CASE 1

### 7. Enter analysis data

- In the LIFFT tab, enter the three tasks shown in the reference image.

| Lifting Fatigue Failure Tool (LIFFT)    Distal Upper Extremity Tool (DUET)    Shoulder Tool (ST) |                |           |                |                            |                     |                  |
|--------------------------------------------------------------------------------------------------|----------------|-----------|----------------|----------------------------|---------------------|------------------|
| Task #                                                                                           | Lever Arm (in) | Load (lb) | Moment (ft.lb) | Repetitions (per work day) | Damage (cumulative) | % Total (damage) |
| 1                                                                                                | 14             | 10        | 11.7           | 420                        | 0.0012              | 5.1              |
| 2                                                                                                | 18             | 44        | 66.0           | 75                         | 0.0033              | 14.0             |
| 3                                                                                                | 24             | 54        | 108.0          | 50                         | 0.0190              | 80.9             |

14                      10                      420  
 18                      44                      75  
 24                      54                      50

- Click "Calculate"

- Go to the DUET tab, enter the tasks shown in the reference image.

| Lifting Fatigue Failure Tool (LIFFT)    Distal Upper Extremity Tool (DUET)    Shoulder Tool (ST) |                  |                            |                     |                  |
|--------------------------------------------------------------------------------------------------|------------------|----------------------------|---------------------|------------------|
| Task #                                                                                           | OHNI-Res Scale   | Repetitions (per work day) | Damage (cumulative) | % Total (damage) |
| 1                                                                                                | 2: Easy          | 1000                       | 0.00137             | 1.0              |
| 2                                                                                                | 4: Somewhat Easy | 700                        | 0.00883             | 6.5              |
| 3                                                                                                | 8: Hard          | 120                        | 0.12645             | 92.5             |

Easy : 1000

Somewhat Easy : 700

Hard : 120

- Click "Calculate."

- Go to the ST tab, enter the three tasks shown in the reference image.

| Lifting Fatigue Failure Tool (LIFFT)    Distal Upper Extremity Tool (DUET)    Shoulder Tool (ST) |                |                |           |                |                            |                     |                  |
|--------------------------------------------------------------------------------------------------|----------------|----------------|-----------|----------------|----------------------------|---------------------|------------------|
| Task #                                                                                           | Type of Task   | Lever Arm (in) | Load (lb) | Moment (ft.lb) | Repetitions (per work day) | Damage (cumulative) | % Total (damage) |
| 1                                                                                                | Handling Loads | 16             | 2         | 8.4            | 2880                       | 0.00428             | 100.0            |
| 2                                                                                                | Handling Loads |                |           | 0.0            |                            | 0.00000             | 0.0              |

Handling Loads:                      16                      2                      2880


- Click "Calculate"

**\*Expected result:** Each tool calculates successfully and displays results on screen.

## CASE 1

### 8. Save and reopen the project


- Click Project > Save.
- Confirm any save notifications.
- Close the software.
- Reopen the software.
- Click Open (folder icon).
- Open the previously saved project.



**\*Expected result:** The project reopens with the previously entered worker, job assignments, and analysis data loaded correctly.

### 9. Export the file to CSV

- Click on "Project" at the top and select "Export Selected Tool as CSV format"




- Find a location to save your file, it will have the selected tool results for all workers in the project.

**\*Expected result:** The user will have a csv file with the results of the analyses.

## CASE 2

# Project Management




**Objective:** Duplicate existing analyses from one worker to another worker who works in the same plant, section, and line, but at a different station.

### Preconditions

- The project from Case 1 already exists.
- **Worker\_01** contains saved analyses.

### Steps

1. Launch the software
  - Open the existing project
  - Open the project created in Case 1.



- Confirm that **Worker\_01** and the previously entered data are loaded.

## CASE 2


### 2. Create a second worker

- Open the worker editing window.
- Click "New".
  - Enter the Worker ID: **Worker\_02**
  - Date of Birth: *06/06/2000*
  - Sex: *Female*
- Click Save.
- Close the worker window.



### 3. Switch to the new worker

- On the main interface, use the worker drop-down list.



- Select Worker\_02.

\***Expected result:** Worker\_02 is displayed on the main screen, but the analysis tabs are empty.


### 4. Transfer data from Worker\_01

- Switch back to Worker\_01.
- Click the Transfer Data button.




## CASE 2


- In the Transfer Worker Tool Data window:



- Select **Worker\_02** as the destination worker.
- Change the destination station to **Testing\_Station\_02**.



- Keep "Copy Data" selected.
- Click "Transfer".
- Confirm the transfer for each tool when prompted.
- Close the transfer window.



**\*Expected result:** The analyses from Worker\_01 are copied to Worker\_02 under Testing\_Station\_02.

## CASE 2

### 5. Verify transferred data

- Select Worker\_02 on the main interface.

\*If no analysis appears immediately, change the station to **Testing\_Station\_02**.

- Open the "Shoulder Tool" tab.
- Update the input values according to the reference image.

| Lifting Fatigue Failure Tool (LIFFT)   Distal Upper Extremity Tool (DUET)   Shoulder Tool (ST) |                |                |           |                |                            |                     |                  |
|------------------------------------------------------------------------------------------------|----------------|----------------|-----------|----------------|----------------------------|---------------------|------------------|
| Task #                                                                                         | Type of Task   | Lever Arm (in) | Load (lb) | Moment (ft.lb) | Repetitions (per work day) | Damage (cumulative) | % Total (damage) |
| 1                                                                                              | Handling Loads | 18             | 5         | 14.0           | 2000                       | 0.01388             | 86.6             |
| 2                                                                                              | Handling Loads | 16             | 2         | 8.4            | 1440                       | 0.00214             | 13.4             |
| 3                                                                                              | Handling Loads |                |           | 0.0            |                            | 0.00000             | 0.0              |

Handling Loads:      18              5              2000

Handling Loads:      16              2              1440

- Click "Calculate"

### 6. Save the project


- Click the "Save" button in the top toolbar.
- Confirm the changes.

**\*Expected result:** The project is saved with both workers and their corresponding analyses.



## CASE 3

# Layout View



**Objective:** Open the layout view and load a predefined layout.


### Preconditions

- The project from Case 2 is already open.
- The predefined layout file exists in the assets folder.
- At least two workers are available in the project.
- Worker assignments have already been saved in the project.

### Steps


#### 1. Open Layout View

- With the project open, click Layout to enter PLOT's Layout View.



- Confirm that the Layout View window opens successfully. The following window will appear:


## CASE 3



- At the top of the window, identify the filtering sections for Plant, Section, Line, Station, and Shift.



- At the top left, identify the panel used to select the different analysis tools. The displayed worker colors and results will depend on the selected tool:





**\*Expected result:** The Layout View opens and the user can identify the filtering options and tool-selection panel.

## CASE 3


### 2. Load a predefined layout

- Click the Open Layout icon on the left side of the Layout View.
- Browse to:
  - **C:\Users\user01\Desktop\ErgoTools-plot\assets**

\*If your Windows username is different, update the folder path accordingly.




- Select **layout01**.
- Click "Open".
- Back in the Layout View, click "Save" to save the loaded layout.
- Confirm that a notification appears indicating that the plant image has been saved successfully.




## CASE 3

### 3. Display workers in the layout

- Confirm that no workers appear initially in the layout.
- In the bottom-left corner of the screen, locate the Worker section.
- In the "Worker ID" drop-down list, select **Worker\_01**.
- Check the Visible option to make the worker appear in the layout



- Confirm that the worker appears as a geometric figure, with the shape based on sex and the color based on the currently selected analysis tool (Circle for female, triangle for male).



- Select **Worker\_02** from the Worker ID drop-down list.
- Check the Visible option for **Worker\_02**.
- Confirm that the second worker also appears in the layout.


**\*Expected result:** The selected workers become visible in the layout.

## CASE 3

### 4. Reposition workers in the layout

- Click and hold the figure for **Worker\_02** (Circle).
- Drag the figure to the desired location, for example just below the Assembly section shown in the reference image.
- Click and hold the figure for **Worker\_01** (Triangle)
- Drag the figure to the desired location, for example next to **Worker\_02**

**\*Expected result:** Both worker icons can be moved to user-defined positions within the layout



### 5. Adjust worker icon scale

- In the bottom section of the Layout View, locate the Scale options.
- Above "Save" is the "Scale" for an individual worker
- Above "Save All" is the "Scale" for all workers




- Change the "Scale" above the "Save All" to 0.5.
- Click "Save All"
- Confirm that the worker icons are resized and that a confirmation message appears.

**\*Expected results:** The visible worker icons are resized successfully.


### 6. Save and close the layout

- Confirm that the layout shows both workers in their selected positions.
- Close the Layout View window.
- Save the project.



## CASE 4

# Large Project Navigation, Layout Review, and Export



**Objective:** Load a project with a large worker database, navigate the layout using filters and tools, inspect individual workers from the layout, and export the layout image and displayed data successfully.

### Preconditions

- The Case 4 folder is available and contains the required project files.
- The file **Case\_04.ergprj** is available inside the Case 4 folder.
- The database is already populated with workers and analysis results.
- The software shortcut is available on the desktop.

### Steps



1. Launch the software
  - Double-click **Run\_ergotools – Shortcut** on the desktop
  - If needed, drag the top bar of the software window to center it on the screen.

**\*Expected result:** The software opens successfully.

## CASE 4

### 2. Load a project

- Click Project in the upper-left corner.
- Click Open, and select Case 4 folder, inside open the file **Case\_04.ergprj**.
- Click Open.
- Confirm that the project loads successfully.
- Click Layout to open the Layout View.




**\*Expected result:** The populated project opens successfully and the Layout View can be accessed.

### 3. Review the Layout View interface

- Confirm that the Layout View opens successfully.



## CASE 4





- Identify the filtering sections available in the layout.
- Identify the tool-selection area used to switch between analysis views, such as LIFFT and DUET.
- Confirm that worker information and plots are visible in the populated layout environment.

**\*Expected result:** The user can identify the main layout controls, filters, plots, and worker visualization area.

### 4. Navigate between analysis tools

- Select the LIFFT view in the Layout View.
- Observe the displayed worker results and plots.
- Switch to the DUET view.
- Apply the desired filter.



Layout with DUET filter

- Switch back to LIFFT.
- Apply the filter again.

**\*Expected result:** The layout updates when different analysis tools are selected, and the displayed worker information reflects the selected tool.

## CASE 4

### 5. Apply and clear worker filters

- In the worker filtering section, check "Worker" then, locate the Sex filter.
- Change the filter from Both to Female.
- Click "Apply Filters"
- Confirm that only female workers remain displayed.

☒ Worker

Sex: Female Both Male

Age: Female Both Male

Weight:  to

Height:  to

Clear Filters

Apply Filters




- Change the filter back from Female to Both.
- Click "Apply Filters"
- Confirm that the full worker population is displayed again

**\*Expected result:** The layout correctly updates when the worker filter is changed and reapplied.



### 6. Review layout plots

- Locate the plot showing "Total Worker Distribution by Tool."



## CASE 4

- Change the displayed plot to the "Worker Risk Distribution by Gender & Tool."
- The plot will change without having to click on "Apply Filters"
- Click the plot to open it in a larger window.
- Review the enlarged plot.
- Save the enlarged plot as an image by selecting a folder, use as file name **Testing\_Risk\_By\_Gender\_And\_Tool**.
- Close the enlarged plot window.
- Return to the original plot view for total worker distribution by tool.




**\*Expected result:** The selected plot opens in a larger window and can be saved as an image.

## CASE 4

### 7. Inspect an individual worker from the layout


- In the Layout View, left-click on one worker icon.
- Confirm that worker information appears at the bottom



- Right-click on the same worker icon.
- Select "Load" into Tool Window.
- Confirm that the Layout View closes and the software returns to the main interface.
- Confirm that the selected worker and that worker's analyses are loaded into the tool window.

**\*Expected result:** The selected worker can be loaded directly from the Layout View into the main tool window.

## CASE 4






8. Reopen the layout and export the layout image

- Return to Layout View.
- Click the Camera icon on the left side of the layout.
- In the save window, choose the Desktop as the destination folder.
- Enter the file name **Testing\_Layout\_Image**.
- Save the file.
- Confirm that the layout is exported as a PNG image file.

**\*Expected result:** A PNG image of the layout is saved successfully.


9. Export the displayed layout data

- Click the Export Data icon on the left side of the layout.
- In the save window, choose the Desktop as the destination folder.



## CASE 4

- Enter the file name *Data\_Layout\_01*.
- Save the file.
- A confirmation message will appear.
- Confirm the message, by clicking "OK"



**\*Expected result:** A CSV file containing the displayed layout data is saved successfully.

### 10. Verify exported files

- Open the saved **Layout\_01.png** file from the Desktop.
- Confirm that the image contains the expected layout view.
- Open the saved **Data\_Layout\_01.csv** file from the Desktop.
- Confirm that the file contains the expected exported layout data.

**\*Expected result:** Both export files are created successfully and contain the expected information.

|    | A              | B          | C            | D           | E           | F        | G       | H         | I           | J        | K          | L         | M         | N        | O        | P      | Q         | R             | S | T | U | V | W |
|----|----------------|------------|--------------|-------------|-------------|----------|---------|-----------|-------------|----------|------------|-----------|-----------|----------|----------|--------|-----------|---------------|---|---|---|---|---|
|    | worker_id      | plant_name | section_name | line_name   | station_id  | shift_id | tool_id | total_cum | probability | unit     | first_name | last_name | year_of_b | month_of | day_of_b | gender | worker_hc | worker_weight |   |   |   |   |   |
| 1  | Default        | Default    | Default      | Default     | Default     | 1        | LIFT    | 0.0014    | 23.2        | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 2  | Default        | Default    | Default      | Default     | ST02        | 1        | LIFT    | 0.0014    | 23.2        | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 3  | Default        | Default    | Default      | Default     | ST03        | 1        | LIFT    | 0.0235    | 51.4        | Imperial |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 4  | Default        | Default    | Default      | Default     | ST04        | 1        | LIFT    | 0.0014    | 23.2        | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 5  | Default        | Default    | Default      | Default     | ST05        | 1        | LIFT    | 0.0014    | 23.2        | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 6  | Default        | Default    | Default      | Default     | ST06        | 1        | LIFT    | 0.0014    | 23.2        | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 7  | Default        | Default    | Default      | Default     | ST06        | 1        | LIFT    | 0.0014    | 23.2        | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 8  | Default        | Default    | SecondSec    | SecondLin   | SecondSta   | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 9  | Default        | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 10 | Default        | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 11 | Default        | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 12 | Default        | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 13 | Default        | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 14 | Default        | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.0001    | 8.5         | Metric   |            |           | 2025      | 2        |          | 18     | Female    |               |   |   |   |   |   |
| 15 | SIN001         | Default    | Default      | Default     | Default     | 1        | LIFT    | 0.009     | 40.8        | Imperial | Mauricio   | Henriquez | 2000      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 16 | SIN001         | Default    | Default      | Default     | ST02        | 1        | LIFT    | 0.009     | 40.8        | Imperial | Mauricio   | Henriquez | 2000      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 17 | SIN001         | Default    | Default      | Default     | ST04        | 1        | LIFT    | 0.009     | 40.8        | Imperial | Mauricio   | Henriquez | 2000      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 18 | SIN001         | Default    | Default      | Default     | ST05        | 1        | LIFT    | 0.009     | 40.8        | Imperial | Mauricio   | Henriquez | 2000      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 19 | SIN001         | Default    | Default      | Default     | ST06        | 1        | LIFT    | 0.009     | 40.8        | Imperial | Mauricio   | Henriquez | 2000      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 20 | SIN001         | Default    | ThirdSectic  | ThirdSectic | ThirdSectic | 1        | LIFT    | 0.009     | 40.8        | Imperial | Mauricio   | Henriquez | 2000      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 21 | SIN002         | Default    | Default      | Default     | Default     | 1        | LIFT    | 0.0235    | 51.4        | Imperial | Ivan       | Nail      | 2003      | 2        |          | 5      | Female    |               |   |   |   |   |   |
| 22 | SIN002         | Default    | Default      | Default     | ST03        | 1        | LIFT    | 0.0235    | 51.4        | Imperial | Ivan       | Nail      | 2003      | 2        |          | 5      | Female    |               |   |   |   |   |   |
| 23 | SIN002         | Default    | Default      | Default     | ST04        | 1        | LIFT    | 0.0235    | 51.4        | Imperial | Ivan       | Nail      | 2003      | 2        |          | 5      | Female    |               |   |   |   |   |   |
| 24 | SIN002         | Default    | Default      | Default     | ST05        | 1        | LIFT    | 0.0235    | 51.4        | Imperial | Ivan       | Nail      | 2003      | 2        |          | 5      | Female    |               |   |   |   |   |   |
| 25 | SIN002         | Default    | Default      | Default     | ST06        | 1        | LIFT    | 0.0235    | 51.4        | Imperial | Ivan       | Nail      | 2003      | 2        |          | 5      | Female    |               |   |   |   |   |   |
| 26 | SIN003         | Default    | Default      | Default     | Default     | 1        | LIFT    | 0.0234    | 51.3        | Metric   | John       | Void      | 2003      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 27 | SIN003         | Default    | Default      | Default     | ST02        | 1        | LIFT    | 0.0234    | 51.3        | Metric   | John       | Void      | 2003      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 28 | SIN003         | Default    | Default      | Default     | ST03        | 1        | LIFT    | 0.0234    | 51.3        | Metric   | John       | Void      | 2003      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 29 | SIN003         | Default    | Default      | Default     | ST04        | 1        | LIFT    | 0.0234    | 51.3        | Metric   | John       | Void      | 2003      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 30 | SIN003         | Default    | Default      | Default     | ST05        | 1        | LIFT    | 0.0234    | 51.3        | Metric   | John       | Void      | 2003      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 31 | SIN003         | Default    | Default      | Default     | ST06        | 1        | LIFT    | 0.0234    | 51.3        | Metric   | John       | Void      | 2003      | 2        |          | 4      | Male      |               |   |   |   |   |   |
| 32 | SIN004         | Default    | Default      | Default     | Default     | 1        | LIFT    | 0.0158    | 47          | Metric   | Maria      | Fernandez | 2003      | 2        |          | 7      | Female    |               |   |   |   |   |   |
|    | Data Layout 01 |            |              |             |             |          |         |           |             |          |            |           |           |          |          |        |           |               |   |   |   |   |   |