```
entry
                                                        LINENUMBER 819 L0
                                                        ALOAD 0
                                                        GETFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
                                                        LSTORE 5
                                                        LINENUMBER 824 L1
                                                        LLOAD 1
                                                        LCONST 0
                                                        LCMP
                                                        IFGE L2
      L3
                                                                               LINENUMBER 827 L2
      LINENUMBER 825 L3
                                                                              FRAME APPEND [J]
      ALOAD 0
                                                                               ALOAD 0
      INVOKEVIRTUAL com/sleepycat/je/dbi/MemoryBudget.getMaxMemory ()J
                                                                              GETFIELD com/sleepycat/je/dbi/MemoryBudget.totals: Lcom/sleepycat/je/dbi/MemoryBudget$Totals;
      LSTORE 1
      GOTO L4
                                                                              INVOKESTATIC com/sleepycat/je/dbi/MemoryBudget$Totals.access$200 (Lcom/sleepycat/je/dbi/MemoryBudget$Totals;J)V
                                          LINENUMBER 847 L4
                                          FRAME SAME
                                          ALOAD 0
                                          GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getSharedCache ()Z
                                          IFEQ L5
                  LINENUMBER 848 L6
                  INVOKESTATIC com/sleepycat/je/dbi/DbEnvPool.getInstance ()Lcom/sleepycat/je/dbi/DbEnvPool; INVOKEVIRTUAL com/sleepycat/je/dbi/DbEnvPool.getNSharedCacheEnvironments ()I
                  ISTORE 9
                  LINENUMBER 849 L7
                  ILOAD 3
                  IFEQ L8
                                                                                                 LINENUMBER 854 L5
                                                                                                 FRAME CHOP 3
                                                                    LINENUMBER 850 L9
                                                                                                 LLOAD 1
                                                                    IINC 9 1
                                                                                                 LSTORE 7
                                                                   L8
                                                                   LINENUMBER 852 L8
                                                                  FRAME APPEND [T T I]
                                                                   LLOAD 1
                                                                  ILOAD 9
                                                                   I2L
                                                                   LDIV
                                                                  LSTORE 7
                                                                   L10
                                                                   LINENUMBER 853 L10
                                                                   GOTO L11
                                LINENUMBER 866 L11
FRAME APPEND [J]
                                ALOAD 4
                                GETSTATIC com/sleepycat/je/config/EnvironmentParams.LOG_MEM_SIZE: Lcom/sleepycat/je/config/LongConfigParam;
                                L12
                                LINENUMBER 867 L12
                                INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getLong (Lcom/sleepycat/je/config/LongConfigParam;)J
                                LSTORE 9
                                L13
                                LINENUMBER 868 L13
                                LLOAD 9
                                LCONST_0
LCMP
                                IFNE L14
                                                                   L14
                                                                   LINENUMBER 870 L14
                                                                   FRAME APPEND [J]
                                                                   LLOAD 9
                                                                   LLOAD 7
                                                                   LDC 2
                                                                   LDIV
                                                                   LCMP
                                                                   IFLE L16
                                                                                              L15
                                                                   L17
                                                                                              LINENUMBER 869 L15
                                                                   LINENUMBER 871 L17
LLOAD 7
                                                                                              LLOAD 7
                                                                                              ICONST_4
                                                                   LDC 2
                                                                                              LSHR
                                                                   LDIV
                                                                                              LSTORE 9
                                                                   LSTORE 9
                                                                                              GOTO L16
                    L16
                    LINENUMBER 879 L16
                    FRAME SAME
                     ALOAD 4
                     GETSTATIC com/sleepycat/je/config/EnvironmentParams.NUM_LOG_BUFFERS: Lcom/sleepycat/je/config/IntConfigParam;
                     L18
                     LINENUMBER 880 L18
                     INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
                     ISTORE 11
                    L19
                     LINENUMBER 881 L19
                     LLOAD 9
                     ILOAD 11
                    LDIV
                     LSTORE 12
                     L20
                    LINENUMBER 882 L20
                     ALOAD 4
                     GETSTATIC com/sleepycat/je/config/EnvironmentParams.LOG_BUFFER_MAX_SIZE: Lcom/sleepycat/je/config/IntConfigParam;
                     LINENUMBER 883 L21
                    INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
                     ISTORE 14
                     L22
                    LINENUMBER 884 L22
                    LLOAD 12
                     ILOAD 14
                     I2L
                    LCMP
                    IFLE L23
                                                           L23
                                                           LINENUMBER 887 L23
                                                           FRAME APPEND [I J I]
                                                           LLOAD 12
                                                           LDC 2048
                                                           LCMP
                                                           IFGE L26
                                                                                       L24
                                                           L27
                                                                                      LINENUMBER 885 L24
                                                           LINENUMBER 889 L27
                                                                                      ILOAD 14
                                                           LDC 2048
                                                                                      I2L
                                                           LSTORE 12
                                                                                      LSTORE 12
                                                                                      L25
                                                           LINENUMBER 890 L28
                                                                                      LINENUMBER 886 L25
                                                                                       ILOAD 11
                                                           ILOAD 11
                                                           I2L
                                                                                      I2L
                                                                                      LLOAD 12
                                                           LLOAD 12
                                                           LMUL
                                                                                       LMUL
                                                                                      LSTORE 9
                                                           LSTORE 9
                                                                                      GOTO L26
L26
LINENUMBER 893 L26
FRAME SAME
LLOAD 1
ALOAD 0
GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
LINENUMBER 895 L29
INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager; GETSTATIC com/sleepycat/je/config/EnvironmentParams.EVICTOR_CRITICAL_PERCENTAGE : Lcom/sleepycat/je/config/IntConfigParam;
LINENUMBER 896 L30
INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
LMUL
LDC 100
LDIV
LSTORE 15
L31
LINENUMBER 898 L31
LLOAD 7
ALOAD 0
GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
LINENUMBER 900 L32
INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager;
GETSTATIC com/sleepycat/je/config/EnvironmentParams.CLEANER_DETAIL_MAX_MEMORY_PERCENTAGE : Lcom/sleepycat/je/config/IntConfigParam;
LINENUMBER 901 L33
INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
LMUL
LDC 100
LDIV
LSTORE 17
L34
LINENUMBER 903 L34
ALOAD 4
GETSTATIC com/sleepycat/je/config/EnvironmentParams.MIN_TREE_MEMORY: Lcom/sleepycat/je/config/LongConfigParam;
LINENUMBER 904 L35
INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getLong (Lcom/sleepycat/je/config/LongConfigParam;)J
LLOAD 7
LLOAD 9
LSUB
INVOKESTATIC java/lang/Math.min (JJ)J
LSTORE 19
L36
LINENUMBER 912 L36
ALOAD 0
LLOAD 9
PUTFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
LINENUMBER 913 L37
ALOAD 0
GETFIELD com/sleepycat/je/dbi/MemoryBudget.totals: Lcom/sleepycat/je/dbi/MemoryBudget$Totals;
INVOKESTATIC com/sleepycat/je/dbi/MemoryBudget$Totals.access$300 (Lcom/sleepycat/je/dbi/MemoryBudget$Totals;J)V
LINENUMBER 914 L38
ALOAD 0
LLOAD 17
PUTFIELD com/sleepycat/je/dbi/MemoryBudget.trackerBudget: J
LINENUMBER 915 L39
ALOAD 0
LLOAD 19
PUTFIELD com/sleepycat/je/dbi/MemoryBudget.minTreeMemoryUsage: J
LINENUMBER 918 L40
ALOAD 0
GETFIELD com/sleepycat/je/dbi/MemoryBudget.totals: Lcom/sleepycat/je/dbi/MemoryBudget$Totals;
ALOAD 0
GETFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
LLOAD 5
INVOKEVIRTUAL com/sleepycat/je/dbi/MemoryBudget$Totals.updateCacheUsage (J)Z
LINENUMBER 925 L41
ILOAD 3
IFNE L42
                      LLOAD 5
                      ALOAD 0
                      GETFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
                      LCMP
                      IFEQ L42
                                                                       L42
                                                                       LINENUMBER 928 L42
                                                                       FRAME APPEND [J J J]
                                                                       RETURN
                                                                       L44
```

L43 LINENUMBER 926 L43 ALOAD 0 GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getLogManager ()Lcom/sleepycat/je/log/LogManager; ALOAD 4 INVOKEVIRTUAL com/sleepycat/je/log/LogManager.resetPool (Lcom/sleepycat/je/dbi/DbConfigManager;)V exit