```
entry
```

```
L0
LINENUMBER 4686 L0
LCONST_0
LSTORE 2
L1
LINENUMBER 4692 L1
ALOAD 0
GETFIELD com/sleepycat/je/tree/IN.entryKeys : Lcom/sleepycat/je/tree/INKeyRep;
INVOKEVIRTUAL com/sleepycat/je/tree/INKeyRep.accountsForKeyByteMemUsage ()Z
IFNE L2
```

```
L3
LINENUMBER 4698 L3
ALOAD 0
GETFIELD com/sleepycat/je/tree/IN.entryKeys : Lcom/sleepycat/je/tree/INKeyRep;
ILOAD 1
INVOKEVIRTUAL com/sleepycat/je/tree/INKeyRep.get (I)Ljava/lang/Object;
CHECKCAST [B
ASTORE 4
L4
LINENUMBER 4699 L4
ALOAD 4
IFNULL L2
```

```
L5
LINENUMBER 4700 L5
LLOAD 2
ALOAD 4
ARRAYLENGTH
INVOKESTATIC com/sleepycat/je/dbi/MemoryBudget.byteArraySize (I)I
I2L
LADD
LSTORE 2
```

```
L2
LINENUMBER 4704 L2
FRAME APPEND [J]
ALOAD 0
GETFIELD com/sleepycat/je/tree/IN.entryTargets : Lcom/sleepycat/je/tree/INTargetRep;
ILOAD 1
INVOKEVIRTUAL com/sleepycat/je/tree/INTargetRep.get (I)Ljava/lang/Object;
CHECKCAST com/sleepycat/je/tree/Node
ASTORE 4
L6
LINENUMBER 4705 L6
ALOAD 4
IFNULL L7
```

```
L8
LINENUMBER 4706 L8
LLOAD 2
ALOAD 4
INVOKEVIRTUAL com/sleepycat/je/tree/Node.getMemorySizeIncludedByParent ()J
LADD
LSTORE 2
```

```
L7
LINENUMBER 4708 L7
FRAME APPEND [com/sleepycat/je/tree/Node]
LLOAD 2
LRETURN
L9
```

```
exit
```