```
entry
                                                                     LINENUMBER 819 L0
                                                                     ALOAD 0
                                                                     GETFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
                                                                     LSTORE 5
                                                                     L1
                                                                     LINENUMBER 824 L1
                                                                     LLOAD 1
                                                                     LCONST_0
                                                                     LCMP
                                                                     IFGE L2
                                                                                                               L3
LINENUMBER 827 L2
                                                                                                               LINENUMBER 825 L3
FRAME APPEND [J]
                                                                                                                ALOAD 0
ALOAD 0
                                                                                                               INVOKEVIRTUAL com/sleepycat/je/dbi/MemoryBudget.getMaxMemory ()J
GETFIELD com/sleepycat/je/dbi/MemoryBudget.totals: Lcom/sleepycat/je/dbi/MemoryBudget$Totals;
                                                                                                               LSTORE 1
                                                                                                               GOTO L4
INVOKESTATIC com/sleepycat/je/dbi/MemoryBudget$Totals.access$200 (Lcom/sleepycat/je/dbi/MemoryBudget$Totals;J)V
                                                       LINENUMBER 847 L4
                                                        FRAME SAME
                                                        ALOAD 0
                                                        GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                                        INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getSharedCache ()Z
                                                        IFEQ L5
                                                                                LINENUMBER 848 L6
                                                                                INVOKESTATIC com/sleepycat/je/dbi/DbEnvPool.getInstance ()Lcom/sleepycat/je/dbi/DbEnvPool;
                                                                                INVOKEVIRTUAL com/sleepycat/je/dbi/DbEnvPool.getNSharedCacheEnvironments ()I
                                                                                ISTORE 9
                                                                                L7
                                                                                LINENUMBER 849 L7
                                                                                ILOAD 3
                                                                                IFEQ L8
                                                                    LINENUMBER 854 L5
                                                                     FRAME CHOP 3
                                                                                                                LINENUMBER 850 L9
                                                                    LLOAD 1
                                                                                                                 IINC 9 1
                                                                     LSTORE 7
                                                                                                LINENUMBER 852 L8
                                                                                                FRAME APPEND [T T I]
                                                                                                LLOAD 1
                                                                                                ILOAD 9
                                                                                                I2L
                                                                                                LDIV
                                                                                                LSTORE 7
                                                                                                L10
                                                                                                LINENUMBER 853 L10
                                                                                                GOTO L11
                                          L11
                                          LINENUMBER 866 L11
                                          FRAME APPEND [J]
                                          ALOAD 4
                                          GETSTATIC com/sleepycat/je/config/EnvironmentParams.LOG_MEM_SIZE : Lcom/sleepycat/je/config/LongConfigParam;
                                          L12
                                          LINENUMBER 867 L12
                                          INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getLong (Lcom/sleepycat/je/config/LongConfigParam;)J
                                          LSTORE 9
                                          L13
                                          LINENUMBER 868 L13
                                          LLOAD 9
                                          LCONST 0
                                          LCMP
                                          IFNE L14
                                                                            L14
                                                                            LINENUMBER 870 L14
                                                                            FRAME APPEND [J]
                                                                            LLOAD 9
                                                                            LLOAD 7
                                                                            LDC 2
                                                                            LDIV
                                                                            LCMP
                                                                            IFLE L16
                                                                                                       L15
                                                                            L17
                                                                                                       LINENUMBER 869 L15
                                                                            LINENUMBER 871 L17
                                                                                                       LLOAD 7
                                                                            LLOAD 7
                                                                                                       ICONST_4
                                                                            LDC 2
                                                                                                       LSHR
                                                                            LDIV
                                                                                                       LSTORE 9
                                                                            LSTORE 9
                                                                                                       GOTO L16
                               L16
                               LINENUMBER 879 L16
                               FRAME SAME
                               ALOAD 4
                               GETSTATIC com/sleepycat/je/config/EnvironmentParams.NUM_LOG_BUFFERS: Lcom/sleepycat/je/config/IntConfigParam;
                               L18
                               LINENUMBER 880 L18
                               INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
                               ISTORE 11
                               L19
                               LINENUMBER 881 L19
                               LLOAD 9
                               ILOAD 11
                               I2L
                               LDIV
                               LSTORE 12
                               L20
                               LINENUMBER 882 L20
                               ALOAD 4
                               GETSTATIC com/sleepycat/je/config/EnvironmentParams.LOG_BUFFER_MAX_SIZE : Lcom/sleepycat/je/config/IntConfigParam;
                               LINENUMBER 883 L21
                               INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
                               ISTORE 14
                               L22
                               LINENUMBER 884 L22
                               LLOAD 12
                               ILOAD 14
                               I2L
                               LCMP
                               IFLE L23
                                                                                         L23
                                                                                         LINENUMBER 887 L23
                                                                                         FRAME APPEND [I J I]
                                                                                         LLOAD 12
                                                                                         LDC 2048
                                                                                         LCMP
                                                                                         IFGE L26
                                                               L24
                                                                                         L27
                                                               LINENUMBER 885 L24
                                                               ILOAD 14
                                                                                         LINENUMBER 889 L27
                                                                                         LDC 2048
                                                               I2L
                                                               LSTORE 12
                                                                                         LSTORE 12
                                                               L25
                                                                                         L28
                                                               LINENUMBER 886 L25
                                                                                         LINENUMBER 890 L28
                                                               ILOAD 11
                                                                                         ILOAD 11
                                                               I2L
                                                                                         I2L
                                                               LLOAD 12
                                                                                         LLOAD 12
                                                               LMUL
                                                                                         LMUL
                                                               LSTORE 9
                                                                                         LSTORE 9
                                                               GOTO L26
                                L26
                                LINENUMBER 893 L26
                                FRAME SAME
                                LLOAD 1
                                ALOAD 0
                                GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                L29
                                LINENUMBER 895 L29
                                INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager; GETSTATIC com/sleepycat/je/config/EnvironmentParams.EVICTOR_CRITICAL_PERCENTAGE : Lcom/sleepycat/je/config/IntConfigParam;
                                LINENUMBER 896 L30
                                INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
                                LMUL
                                LDC 100
                                LDIV
                                LSTORE 15
                                L31
                                LINENUMBER 898 L31
                                LLOAD 7
                                ALOAD 0
                                GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                LINENUMBER 900 L32
                                INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager;
GETSTATIC com/sleepycat/je/config/EnvironmentParams.CLEANER_DETAIL_MAX_MEMORY_PERCENTAGE : Lcom/sleepycat/je/config/IntConfigParam;
                                LINENUMBER 901 L33
                                INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I
                                I2L
                               LMUL
                                LDC 100
                                LDIV
                                LSTORE 17
                                L34
                                LINENUMBER 903 L34
                                ALOAD 4
                                GETSTATIC com/sleepycat/je/config/EnvironmentParams.MIN_TREE_MEMORY: Lcom/sleepycat/je/config/LongConfigParam;
                                L35
                                LINENUMBER 904 L35
                                INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getLong (Lcom/sleepycat/je/config/LongConfigParam;)J
                                LLOAD 7
                                LLOAD 9
                                LSUB
                                INVOKESTATIC java/lang/Math.min (JJ)J
                                LSTORE 19
                                L36
                                LINENUMBER 912 L36
                                ALOAD 0
                                LLOAD 9
                                PUTFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
                                L37
                                LINENUMBER 913 L37
                                ALOAD 0
                                GETFIELD com/sleepycat/je/dbi/MemoryBudget.totals: Lcom/sleepycat/je/dbi/MemoryBudget$Totals;
                                INVOKESTATIC com/sleepycat/je/dbi/MemoryBudget$Totals.access$300 (Lcom/sleepycat/je/dbi/MemoryBudget$Totals;J)V
                                L38
                                LINENUMBER 914 L38
                                ALOAD 0
                                LLOAD 17
                                PUTFIELD com/sleepycat/je/dbi/MemoryBudget.trackerBudget: J
                                L39
                                LINENUMBER 915 L39
                                ALOAD 0
                                LLOAD 19
                                PUTFIELD com/sleepycat/je/dbi/MemoryBudget.minTreeMemoryUsage: J
                                L40
                                LINENUMBER 918 L40
                                ALOAD 0
                                GETFIELD com/sleepycat/je/dbi/MemoryBudget.totals: Lcom/sleepycat/je/dbi/MemoryBudget$Totals;
                                ALOAD 0
                                GETFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
                                LLOAD 5
                                LSUB
                                INVOKEVIRTUAL com/sleepycat/je/dbi/MemoryBudget$Totals.updateCacheUsage (J)Z
                                POP
                                LINENUMBER 925 L41
                                ILOAD 3
                                IFNE L42
                                                     LLOAD 5
                                                     ALOAD 0
                                                     GETFIELD com/sleepycat/je/dbi/MemoryBudget.logBufferBudget: J
                                                     LCMP
                                                     IFEQ L42
         L43
         LINENUMBER 926 L43
          ALOAD 0
         GETFIELD com/sleepycat/je/dbi/MemoryBudget.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
         INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getLogManager ()Lcom/sleepycat/je/log/LogManager;
          ALOAD 4
         INVOKEVIRTUAL com/sleepycat/je/log/LogManager.resetPool (Lcom/sleepycat/je/dbi/DbConfigManager;)V
                                                                                                     L42
                                                                                                     LINENUMBER 928 L42
```

exit

FRAME APPEND [J J J]

RETURN

L44