



USER GUIDE · PART 06

Owner, Team & Settings

Your team, roles, company profile, AI training and guest links

Owner, Team & Settings

This is the back-office of Fieldscale — where the owner sets up the company and controls who can use the app. You add your crew and office staff as logins, decide what each can see, set your company name and logo, keep a backup, and invite prospects to try Takeoff. If you run the business, this is your control room.

Team / Users — the "Owner" page

The Owner page (titled "*Your Team*") lists everyone in your company and how they're using Fieldscale — **activity and usage only, never anyone's project contents**. Only **owners and admins** can manage it.

The four roles, in plain words

Owner

You, the business. One per company. Can do everything, always sees financials, and **can't be changed, disabled, or deleted** — the app protects the owner so you can never lock yourself out.

Administrator

A trusted right hand (office manager, partner). Sees the whole app and can add, change, disable, delete, and reset other accounts — including other admins. Can't touch the owner account.

Member

A normal office/estimating user. Sees the whole app but **can't manage users**. The only role with the "sees \$" money toggle.

Field employee

Crew in the field, **locked to job work only**: their jobs, the schedule, daily logs, time, task check-offs, receipts, and photos — nothing else. No pricing, invoices, reports, or settings. This lock is enforced by the server, not just hidden.

Managing your team

Add a teammate

Type a username and temporary password (8+ chars) and pick a role. Fieldscale doesn't email logins — you hand them over directly, and they change the password after signing in. New accounts land in **your** company only.

Change roles

A dropdown per user, with a confirmation and extra warnings when promoting to Admin or demoting to Field.

"Sees \$" toggle

For members only — leave it on and they see costs, profit, and reports; turn it off to hide the money views (good for a junior estimator or coordinator).

Disable vs. delete

Disable switches an account off (they can't log in, sessions cut immediately) but keeps the account and history — reversible with Enable. Delete removes the login permanently, though the company's shared projects and estimates stay.

Reset password

Set a new temporary password; this signs the person out everywhere so the old one stops working. Passwords are one-way encrypted — nobody can view them, so a reset is the only way to help someone in.

Guardrails

You can't disable, demote, or delete your own account, and you can't remove the last remaining admin — the app makes you promote someone else first.

Backup, security & activity

Backup & Export

Download backup gives you one file with everything hard to replace — estimates, price book, takeoff measurements, and your company profile. **Restore from file** re-imports it. (Plan PDFs aren't included — you have the originals.)

Security & backups card

A plain-English health check: whether the login secret is set, security headers are on, and when the last automatic backup ran (backups run daily). Includes a "Back up now" button.

Recent activity (audit log)

A running log of logins and important changes — who did what and when — newest first, for owners/admins only.

Company profile

Set this once and it auto-fills the top of every new estimate and prints on your PDFs, so you never retype it. It holds:

Logo & details

Upload a logo (used as proposal letterhead and in the app header), plus company name, phone, email, license #, website, and address. The company name is the source of truth for branding across the app.

Auto-numbering

Set the starting **invoice**, **job**, and **work-order** numbers, with any prefix and leading zeros; new documents count up company-wide.

Team & labor rates

A quick crew list with hourly rates (a lighter view of the Employees page).

Markup by category & tax rules

Charge different markup per trade (by CSI code) and choose which trades are taxable; matching estimate lines use these instead of the default.

Contract template

The boilerplate used when you generate a contract from an accepted estimate, with fill-in placeholders like {{client}}, {{total}}, {{scope}}. Resettable to default.

Website lead form

A shareable/embeddable "Request a Quote" link; every submission becomes a new lead tagged "Website form."

Employees

The full crew roster — deeper than the Team page and different in purpose. The **Team page manages logins** (who can sign in and what they see); the **Employees page manages people records** for job costing and dispatch, whether or not they have a login.

For each person you track name, role/trade, charged hourly rate, email, phone, payroll #, and certifications with expiry. Rates here fill in automatically when you log time on a job, and certifications get automatic **"expiring" (within 30 days) and "expired"** flags so you don't send someone out with a lapsed card. Everyone can view the roster, but only the owner or an admin can edit it.

AI Training

A behind-the-scenes dashboard showing Fieldscale learning to read plans and measure them automatically. Every takeoff you do quietly adds labeled examples (a picture of the sheet plus the marks you made), and this page is the growing pile the model learns from.

Owner-only

Enabled just for the owner account; everyone else sees a "only available on the owner account" note.

Customer work is never collected

Guest/prospect takeoffs are never gathered — only your own.

What it shows

Tiles for sheets and marks collected, progress bars toward targets per measurement type, a breakdown by type/trade, recent-sheet thumbnails, and an "Export dataset" button.

It improves as you work

The more takeoffs you do, the more examples accumulate — and the better Fieldscale gets at auto-measuring future plans. The tool speeds up over time from your real work.

Guest takeoff links

Hand a prospect a link to **try the Takeoff tool** without ever exposing your data. On the Owner page, the **Guest takeoff links** card has **Create guest link** — you get a URL to copy and send, and the card shows how many people joined and how many are active.

Isolated sandbox

Each guest gets their own brand-new, empty company with only Takeoff turned on. They can **never** see your projects, customers, or estimates.

Locked everywhere else

Every other menu shows but is locked — the server blocks guests from anything but takeoff, so it can't be bypassed.

One link, many guests

The same link works for multiple prospects, each in a separate sandbox.

Revoke

Click Revoke to instantly stop new sign-ups on that link and disable everyone who already joined.

Platform admin view

If you're the platform owner (the very first account), the Owner page shows two extra sections: **All Companies** (every company on the platform with counts only — never their data — and per-company module toggles for Takeoff/Estimating/Invoicing/Jobs) and **Every Login** (every account's username, company, role, status, and last login; passwords are never shown — you reset to help someone in). Ordinary owners never see these.

Tips & gotchas

- **Fieldscale never emails logins.** When you add a teammate or reset a password, copy the details and give them over yourself.
- **Pick "Field employee" for crew** — the safe default for anyone who shouldn't see pricing, invoices, or reports. The lock is real and server-enforced.

- **Disable before you delete.** Disabling is reversible and keeps everything; deletion is permanent (though shared projects/estimates survive).
- **You can't lock yourself out** — the app blocks demoting/disabling/deleting your own account or removing the last admin.
- **Download a backup regularly.** One click, one file.
- **Set the Company profile early** — name, logo, license, and contact auto-fill every estimate and proposal.
- **Employees vs. Team:** Team = logins and permissions; Employees = people records (rates, certs) for job costing and scheduling.