



lab 11

part b bgp + hand written task on





Router5

Physical
Config
CLI
Attributes

GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0

FastEthernet0/0
Port Status
Bandwidth
Duplex
MAC Address
IP Configuration
IPv4 Address
Subnet Mask
Tx Ring Limit

☒ On
☐ 100 Mbps
☐ 10 Mbps
☒ Auto
☐ Half Duplex
☐ Full Duplex
☒ Auto

0006.2ADA.6391

191.191.0.1
255.255.248.0

10

Equivalent IOS Commands

```

Router(config-if)#no shutdown
Router(config-if)#ip address 192.168.4.6 255.255.255.0
Router(config-if)#ip address 192.168.4.6 255.255.255.252
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
ip address 191.191.0.1 255.255.0.0
Router(config-if)#ip address 191.191.0.1 255.255.248.0
Router(config-if)#

```

☐ Top

lab 11

3



Router4

Physical
Config
CLI
Attributes

GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0

FastEthernet0/0

Port Status
Bandwidth
Duplex
MAC Address
IP Configuration
IPv4 Address
Subnet Mask
Tx Ring Limit

☒ On
☐ 100 Mbps
☐ 10 Mbps
☒ Auto
☐ Half Duplex
☐ Full Duplex
☒ Auto

0001.43C0.2C7C

191.191.8.1

255.255.248.0

10

Equivalent IOS Commands

```

%LINK-5-CHANGED: Interface Serial2/0, changed state to up
ip address 192.168.4.5 255.255.255.252
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
ip address 191.191.8.1 255.255.0.0
Router(config-if)#ip address 191.191.8.1 255.255.248.0
Router(config-if)#

```

☐ Top

lab 11

5



PC2

PhysicalConfigDesktopProgrammingAttributes

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

Bluetooth

FastEthernet0

Port Status

☒ On

Bandwidth

☒ 100 Mbps☐ 10 Mbps

☒ Auto

Duplex

☐ Half Duplex☒ Full Duplex

☒ Auto

MAC Address0040.0BA6.7151

IP Configuration

☐ DHCP

☒ Static

IPv4 Address191.191.16.2

Subnet Mask255.255.248.0

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

Link Local Address: FE80::240:BFF:FEA6:7151

☐ Top

Router5

Physical

Config

CLI

Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

INTERFACE

FastEthernet0/0

FastEthernet1/0

Serial2/0

Serial3/0

FastEthernet4/0

FastEthernet5/0

Serial2/0

Port Status

Duplex

Clock Rate

IP Configuration

IPv4 Address

Subnet Mask

Tx Ring Limit

Serial2/0

Port Status

Duplex

Clock Rate

IP Configuration

IPv4 Address

Subnet Mask

Tx Ring Limit

Equivalent IOS Commands

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet1/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#

Top

Router5

Physical

Config

CLI

Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

INTERFACE

FastEthernet0/0

FastEthernet1/0

Serial2/0

Serial3/0

FastEthernet4/0

FastEthernet5/0

FastEthernet0/0

Port Status

☒ On

Bandwidth

☒ 100 Mbps

☐ 10 Mbps

Duplex

☐ Half Duplex

☒ Full Duplex

MAC Address

0006.2ADA.6391

IP Configuration

IPv4 Address

191.191.0.1

Subnet Mask

255.255.248.0

Tx Ring Limit

10

Equivalent IOS Commands

Router(config)#interface Serial2/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet1/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0


Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#

Top



```

Router(config-if)#
Router(config-if)#exit
Router(config)#router bgp 71
Router(config-router)#neighbor 192.168.4.1 remote-as 1
Router(config-router)%%BGP-5-ADJCHANGE: neighbor 192.168.4.1 Up

Router(config-router)#neighbor 192.168.4.1 remote-as 1
Router(config-router)#neighbor 192.168.4.1 remote-as 79
Router(config-router)#network 191.191.8.0 mask 255.255.248.0
Router(config-router)#exit
Router(config)#do write
Building configuration...
[OK]
Router(config)#
  
```

```

Router(config)#
Router(config)#
Router(config)#interface Serial2/0
Router(config-if)#ex
Router(config)#router bgp 79
Router(config-router)#neighbor 192.168.4.5 remote-as 71
Router(config-router)#%BGP-5-ADJCHANGE: neighbor 192.168.4.5 Up

Router(config-router)#neighbor 192.168.4.5 remote-as 71
Router(config-router)#network 191.191.16.0 mask 255.255.248.0
Router(config-router)#ex
Router(config)#do write
Building configuration...
[OK]
Router(config)#

```

```

Router(config)#ex
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
        i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
        * - candidate default, U - per-user static route, o - ODR
        P - periodic downloaded static route

Gateway of last resort is not set

    191.191.0.0/21 is subnetted, 3 subnets
C       191.191.8.0 is directly connected, FastEthernet0/0
B       191.191.6.0 [20/0] via 192.168.4.2, 00:00:00
B       191.191.16.0 [20/0] via 192.168.4.2, 00:00:00
    192.168.4.0/30 is subnetted, 1 subnets
C       192.168.4.0 is directly connected, Serial2/0

Router#

```

admin dist 20

LSM Calculation Working (Written Form)

Given Network Address: 172.16.0.0/16

Host Requirements:

- LAN2 (Router2): 1990 hosts
- LAN0 (Router0): 1880 hosts
- LAN1 (Router1): 1770 hosts

- WAN Link 1 (R0-R1): 2 hosts
- WAN Link 2 (R1-R2): 2 hosts

Order Subnets by Size (Largest to Smallest)

Table

Order	Subnet	Hosts Required
1	LAN2	1990
2	LAN0	1880
3	LAN1	1770
4	WAN Link 1	2
5	WAN Link 2	2

Step 2: Calculate Host Bits for Each Subnet

Formula: $2^h - 2 \geq \text{Required Hosts}$

LAN2 (1990 hosts):

- Try h=10: $2^{10} - 2 = 1022$
- Try h=11: $2^{11} - 2 = 2046$
- **Host bits = 11, Block size = 2048, Mask = /21 (255.255.248.0)**

LAN0 (1880 hosts):

- Try h=10: 1022
- Try h=11: 2046
- **Host bits = 11, Block size = 2048, Mask = /21**

LAN1 (1770 hosts):

- Try h=10: 1022
- Try h=11: 2046
- **Host bits = 11, Block size = 2048, Mask = /21**

WAN Link 1 (2 hosts):

- Try h=1: 0
- Try h=2: 2
- **Host bits = 2, Block size = 4, Mask = /30 (255.255.255.252)**

WAN Link 2 (2 hosts):

- Same as above: **Host bits = 2, Block size = 4, Mask = /30**

Allocate Network Addresses Sequentially

Starting from **172.16.0.0/16**:

Table

Subnet	Block Size	Network Address	Usable Range	Broadcast
LAN2	2048	172.16.0.0/21	172.16.0.1 – 172.16.7.254	172.16.7.255
LAN0	2048	172.16.8.0/21	172.16.8.1 – 172.16.15.254	172.16.15.255
LAN1	2048	172.16.16.0/21	172.16.16.1 – 172.16.23.254	172.16.23.255
WAN1	4	172.16.24.0/30	172.16.24.1 – 172.16.24.2	172.16.24.3
WAN2	4	172.16.24.4/30	172.16.24.5 – 172.16.24.6	172.16.24.7

Total allocated: 2048 + 2048 + 2048 + 4 + 4 = **6,152 addresses**
Total available in /16: 65,536 addresses

IP Addressing Scheme Table

Table

Device	Interface	IP Address/CIDR	Subnet Mask
Router0	Fa0/0 (LAN0)	172.16.8.1/21	255.255.248.0
	S0/0/0 (to R1)	172.16.24.1/30	255.255.255.252

Device	Interface	IP Address/CIDR	Subnet Mask
Router1	Fa0/0 (LAN1)	172.16.16.1/21	255.255.248.0
	S0/0/0 (to R0)	172.16.24.2/30	255.255.255.252
	S0/0/1 (to R2)	172.16.24.5/30	255.255.255.252
Router2	Fa0/0 (LAN2)	172.16.0.1/21	255.255.248.0
	S0/0/0 (to R1)	172.16.24.6/30	255.255.255.252
PC0	Fa0	172.16.8.2/21	255.255.248.0
PC1	Fa0	172.16.16.2/21	255.255.248.0
PC2	Fa0	172.16.0.2/21	255.255.248.0

part a

The administrative distance of OSPF is 110.

Router0

Physical Config CLI Attributes

IOS

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 192.168.1.129 255.255.255.224
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#int fa1/0
Router(config-if)#ip address 192.168.1.1 255.255.255.192
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

Router(config-if)#exit
Router(config)#int se2/0
Router(config-if)#ip address 192.168.1.213 255.255.255.252
Router(config-if)#no shut

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#
Router(config-if)#exit
Router(config)#int se3/0
Router(config-if)#ip address 192.168.1.209 255.255.255.252
Router(config-if)#no shut

%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Router(config-if)#
Router(config-if)#exit
Router(config)#int fa4/0
Router(config-if)#ip address 192.168.1.221 255.255.255.252
Router(config-if)#no shut
```

Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
Press RETURN to get started!

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip address 192.168.1.65 255.255.255.192
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#int se2/0
Router(config-if)#ip address 192.168.1.214 255.255.255.252
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
^
% Invalid input detected at '^' marker.

Router(config-if)#exit
Router(config)#no shut
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router(config)#int se3/0
Router(config-if)#ip address 192.168.1.217 255.255.255.252
Router(config-if)#no shut

%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Router(config-if)#
```

```

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)# ip address 192.168.1.193 255.255.255.240
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#int fa1/0
Router(config-if)# ip address 192.168.1.161 255.255.255.224
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

Router(config-if)#exit
Router(config)#int se2/0
Router(config-if)#ip address 192.168.1.210 255.255.255.252
Router(config-if)#no shut

Router(config-if)#exit
Router(config)#int se3/0
Router(config-if)#ip address 192.168.1.218 255.255.255.252
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up

Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

```

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa1/0
Router(config-if)#ip address 192.168.1.225 255.255.255.252
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

Router(config-if)#exit
Router(config)#int fa5/0
Router(config-if)# ip address 192.168.1.222 255.255.255.252
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet5/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet5/0, changed state to up
```

IOS Command Line Interface

```
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router ospf 1
Router(config-router)#network 192.168.1.0 0.0.0.63 area 0
Router(config-router)# network 192.168.1.128 0.0.0.31 area 0
Router(config-router)# network 192.168.1.208 0.0.0.3 area 0
Router(config-router)# network 192.168.1.212 0.0.0.3 area 0
Router(config-router)# network 192.168.1.220 0.0.0.3 area 0
Router(config-router)#
```

IOS Command Line Interface

```
Router(config)#router ospf 1
Router(config-router)#network 192.168.1.64 0.0.0.63 area 0
Router(config-router)# network 192.168.1.212 0.0.0.3 area 0
Router(config-router)# network 192.168.1.216 0.0.0.3 area 0
Router(config-router)#
```

Router2

Physical Config CLI Attributes

IOS Command Line Interface

```
Router(config)#router ospf 1
Router(config-router)#network 192.168.1.192 0.0.0.15 area 0
Router(config-router)# network 192.168.1.160 0.0.0.31 area 0
Router(config-router)# network 192.168.1.208 0.0.0.3 area 0
Router(config-router)# network 192.168.1.216 0.0.0.3 area 0
Router(config-router)#
```

Router3

Physical Config CLI Attributes

IOS Command Line Interface

```
Router(config)#router ospf 1
Router(config-router)# network 192.168.1.224 0.0.0.3 area 0
Router(config-router)# network 192.168.1.220 0.0.0.3 area 0
Router(config-router)#
```

PC2

Physical Config **Desktop** Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.66

Subnet Mask 255.255.255.192

Default Gateway 192.168.1.65

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::260:47FF:FE32:5DEC

Default Gateway

Physical Config **Desktop** Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.67

Subnet Mask 255.255.255.192

Default Gateway 192.168.1.65

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::207:ECFF:FE67:67D6

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

PC1

Physical Config **Desktop** Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.194

Subnet Mask 255.255.255.240

Default Gateway 192.168.1.193

DNS Server 0.0.0.0

IPv6 Configuration



Laptop1

Physical

Config

Desktop

Programming

Attributes

IP Configuration

Interface

FastEthernet0

IP Configuration



DHCP



Static

IPv4 Address

192.168.1.162

Subnet Mask

255.255.255.224

Default Gateway

192.168.1.161

DNS Server

0.0.0.0

Laptop0

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.226

Subnet Mask 255.255.255.252

Default Gateway 192.168.1.225

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::260:2FFF:FEC9:665

PC0

Physical Config **Desktop** Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.135

Subnet Mask 255.255.255.224

Default Gateway 192.168.1.129

DNS Server 0.0.0.0

IOS Command Line Interface

```
Router>show ip route
```

```
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
```

```
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
```

```
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
```

```
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
```

```
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
```

```
* - candidate default, U - per-user static route, o - ODR
```

```
P - periodic downloaded static route
```

```
Gateway of last resort is not set
```

```
192.168.1.0/24 is variably subnetted, 10 subnets, 4 masks
```

```
C 192.168.1.0/26 is directly connected, FastEthernet1/0
```

```
O 192.168.1.64/26 [110/65] via 192.168.1.214, 00:06:56, Serial2/0
```

```
C 192.168.1.128/27 is directly connected, FastEthernet0/0
```

```
O 192.168.1.160/27 [110/65] via 192.168.1.210, 00:05:50, Serial3/0
```

```
O 192.168.1.192/28 [110/65] via 192.168.1.210, 00:05:50, Serial3/0
```

```
C 192.168.1.208/30 is directly connected, Serial3/0
```

```
C 192.168.1.212/30 is directly connected, Serial2/0
```

```
O 192.168.1.216/30 [110/128] via 192.168.1.210, 00:05:50, Serial3/0
```

```
[110/128] via 192.168.1.214, 00:05:50, Serial2/0
```

```
C 192.168.1.220/30 is directly connected, FastEthernet4/0
```

```
O 192.168.1.224/30 [110/2] via 192.168.1.222, 00:04:28, FastEthernet4/0
```

IOS Command Line Interface

```
Router>show ip route
```

```
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
```

```
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
```

```
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
```

```
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
```

```
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
```

```
* - candidate default, U - per-user static route, o - ODR
```

```
P - periodic downloaded static route
```

```
Gateway of last resort is not set
```

```
192.168.1.0/24 is variably subnetted, 9 subnets, 4 masks
```

```
O 192.168.1.0/26 [110/65] via 192.168.1.209, 00:03:10, Serial2/0
```

```
O 192.168.1.64/26 [110/65] via 192.168.1.217, 00:03:10, Serial3/0
```

```
O 192.168.1.128/27 [110/65] via 192.168.1.209, 00:03:10, Serial2/0
```

```
C 192.168.1.160/27 is directly connected, FastEthernet1/0
```

```
C 192.168.1.192/28 is directly connected, FastEthernet0/0
```

```
C 192.168.1.208/30 is directly connected, Serial2/0
```

```
O 192.168.1.212/30 [110/128] via 192.168.1.217, 00:03:10, Serial3/0
```

```
[110/128] via 192.168.1.209, 00:03:10, Serial2/0
```

```
C 192.168.1.216/30 is directly connected, Serial3/0
```

```
O 192.168.1.220/30 [110/65] via 192.168.1.209, 00:03:10, Serial2/0
```

IOS Command Line Interface

```
Router>show ip route
```

```
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP  
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP  
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area  
       * - candidate default, U - per-user static route, o - ODR  
       P - periodic downloaded static route
```

```
Gateway of last resort is not set
```

```
    192.168.1.0/24 is variably subnetted, 10 subnets, 4 masks  
O       192.168.1.0/26 [110/2] via 192.168.1.221, 00:08:39, FastEthernet5/0  
O       192.168.1.64/26 [110/66] via 192.168.1.221, 00:08:39, FastEthernet5/0  
O       192.168.1.128/27 [110/2] via 192.168.1.221, 00:08:39, FastEthernet5/0  
O       192.168.1.160/27 [110/66] via 192.168.1.221, 00:03:17, FastEthernet5/0  
O       192.168.1.192/28 [110/66] via 192.168.1.221, 00:03:17, FastEthernet5/0  
O       192.168.1.208/30 [110/65] via 192.168.1.221, 00:08:39, FastEthernet5/0  
O       192.168.1.212/30 [110/65] via 192.168.1.221, 00:08:39, FastEthernet5/0  
O       192.168.1.216/30 [110/129] via 192.168.1.221, 00:03:27, FastEthernet5/0  
C       192.168.1.220/30 is directly connected, FastEthernet5/0  
C       192.168.1.224/30 is directly connected, FastEthernet1/0
```