```
/*
 * This is the .cpp file for the Si7051 sensor
 * The Si7015 is being used as the Globe Thermometer Sensor
 * The bulk of this library was retrieved on line:
 * https://github.com/closedcube/ClosedCube_Si7051_Arduino
 *
 * Part 1 of this library was retrieved on line,
 * while Part 2 was written by MECH 45X Team 26
 *
 * Team 26 does not fully understand how the on line
 * library works, so Part 1 is not commented
 *
 * Team 26 commented Part 2 as they wrote Part 2
 * and understand how the code in Part 2 works
 *
 * Please note that the Globe Thermometer does not
 * measure Mean Radiant Temperature (MRT), it
 * actually measures the globe temperature.
 * MRT is calculate later using air temperature and
 * globe temperature.
 */

#include <Wire.h>
#include "MRT.h"

ClosedCube_Si7051::ClosedCube_Si7051()
{
}

void ClosedCube_Si7051::begin(uint8_t address) {
    _address = address;
    Wire.begin();

    Wire.beginTransmission(_address);
    Wire.write(0xE6);
    Wire.write(0x0);
    Wire.endTransmission();

}

float ClosedCube_Si7051::readT() {
    return readTemperature();
}

float ClosedCube_Si7051::readTemperature() {
    Wire.beginTransmission(_address);
    Wire.write(0xF3);
    Wire.endTransmission();

    delay(15);

    Wire.requestFrom(_address, (uint8_t)2);
    delay(25);
    byte msb = Wire.read();
    byte lsb = Wire.read();

    uint16_t val = msb << 8 | lsb;

    return (175.72*val) / 65536 - 46.85;
}

/*
 * Part 2: Si7051 MECH 45X Team 26 library
 */

bool ClosedCube_Si7051::start_mrt(void) {
    /*
     * Start globe thermometer sensor
     *
```

```
70          * The code will read a value of 128 or greater
71          * if the sensor is broken or disconnected
72          *
73          * The start sequence returns false (sensor does not work)
74          * if a value of 128 is read
75          *
76          * If the value is less than 128, it returns true
77          * (sensor works)
78          *
79          * The code retrieved from the on line library should be improved
80          * to fix this.
81          */
82         begin(ADDR_MRT);
83         delay(500);
84         if(run_mrt() > DEFAULT_AVERAGE) {
85             Serial.println("Failed to start MRT sensor!");
86             return false;
87         } else {
88             Serial.println("Successfully started MRT sensor!");
89             return true;
90         }
91     }
92
93     float ClosedCube_Si7051::run_mrt(void) {
94         /*
95          * Takes globe thermometer measurements until read_count
96          * is exceeded.
97          * Once read_count is exceeded, the average is taken.
98          */
99         read_count = 1;
100
101        while(read_count <= MAX_READ_COUNT) {
102            T_buf[read_count - 1] = readTemperature();
103            Serial.print("Reading #");
104            Serial.print(read_count);
105            Serial.print(": Tg is: ");
106            Serial.println(T_buf[read_count - 1]);
107            read_count ++;
108            delay(250);
109        }
110        if(read_count > MAX_READ_COUNT) {
111            T_ave = 0;
112            for(int k = 0; k < MAX_READ_COUNT; k++) {
113                T_ave = T_ave + T_buf[k];
114            }
115            T_ave = T_ave / MAX_READ_COUNT;
116            Serial.print("Average Tg is: ");
117            Serial.println(T_ave);
118            return(T_ave);
119        }
120    }
121
122    // Getter function for Globe Thermometer average value
123    float ClosedCube_Si7051::get_MRT_ave(void) {return T_ave;}
```