#### \*) <u>Use case specification of Rent Bike:</u>

Renting Bike basic flow:

#	Doer	Action
1	Customer	Scans the barcode and request to rent a bikes
2	Software	Validates barcode
3	Software	Forward to View bikes's information Use Case
4	Software	Asks to choose Payment Method and forwards to Choose Payment Method Use Case
5	Software	Calculates the renting price and asks Customer to confirm
6	Customer	Confirms the transaction
7	Software	Forward to Deduct money Use Case
8	Software	Save the transactions
9	Software	Unlocks the locker, allows customer to use the bike
10	Software	Shows the successful renting message

#### Renting Bike alternative flow:

Location	Doer	Condition	Action	Resume Location
Step 2 of Basic Flow	Software	Invalid barcode	Notifies error to Customer	Step 1 of basic flow
Step 7 of basic flow	Customer	Customer cancel the confirmation	Cancel all the transaction	The use case ends

## \*) <u>Use case specification of Choose Payment Method:</u>

Choose payment method basic flow:

#	Doer	Action
1	Customer	Chooses Payment Methods and Payment Information
2	Software	Calls Validating Information API
3	Interbank	Validates Payment Information and sends status to Software
4	Software	Returns result to Customer

Choose payment method alternative flow:

Location	Doer	Condition	Action	Resume Location
Step 3 of Basic Flow		Error when validating payment information	Sends the failure message to Customer	The use case ends

## \*) <u>Use case specification of Deduct Money:</u>

Deduct Money basic flow:

#	Doer	Action	
1	Software	Calls Check Account API	
2	Interbank	Returns the balance on the customer's credit card	
3	Software	Compares renting price with the balance	
4	Software	Call Deduct money API	
5	Interbank	Deposits money from Customer's account	
6	Software	Returns status of transactions	

# Deduct Money alternative flow:

Location	Doer	Condition	Action	Resume Location
Step 2 of basic flow	Interbank	Interbank Error	Sends the failure message to Software	The use case ends
Step 3 of Basic Flow	Interbank	Not enough money for renting	Sends the failure message to software	The use case ends
Step 5 of Basic Flow	Interbank	Interbank Error	Sends the failure message to software	The use case ends