

```

//////////
//      DTE 3.0      //
//////////
//      --*--      //
//  mpower 2026  //
//////////

```

User Manual

```

,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,
;; build history with exe size result ;;
,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,

;; 0000 init and clear thread - 372 bytes exe
;; 0001 create first API window - 404 bytes
;; 0002 enable quit - 434 bytes
;; 0003 enable X to quit - 445 bytes
;; 0004 enable min and max - 472 bytes
;; 0005 enable mouse resize - 459 bytes
;; 0006 true mouse resize - 451 bytes
;; 0007 start size 800x600 - 455 bytes
;; 0008 add RichEdit20W - 491 bytes
;; 0009 resize RichEdit20W - 533 bytes
;; 0100 add keys/mouse handlers - 536 bytes
;; 0101 add Courier font - 566 bytes
;; 0102 Courier 14 point - 568 bytes
;; 0103 fix runaway process - 573 bytes
;; 0104 enable vertical scroll - 576 bytes
;; 0105 auto vertical scroll - 587 bytes
;; 0106 drop file onto EXE - 709 bytes
;; 0107 leaf filename title - 725 bytes
;; 0108 dirty title marker - 731 bytes
;; 0109 system menu save - 900 bytes
;; 0200 rmv REDIT initial fit - 901 bytes
;; 0201 merge path loops - 999 bytes
;; 0202 share title update - 999 bytes
;; 0203 reorg dispatch and exit - 999 bytes
;; 0204 dispatch exit reorganize - 975 bytes
;; 0205 review for leaks, errors - 975 bytes
;; 0206 fix REDIT capacity - 981 bytes
;; 0207 direct file streaming - 988 bytes
;; 0208 minor changes - 988 bytes
;; 0209 crinkler-aware rewrite - 986 bytes
;; 0300 fix fdirty on click - 985 bytes
;; 0301 opt prsr, addr, data - 794 bytes
;; 0302 add new file ability - 797 bytes
;; 0303 add search ability - 859 bytes
;; 0304 add search wrap - 863 bytes
;; 0305 fixed clean exit (again!) - 864 bytes
;; 0306 fixed client-click crash - 864 bytes
;; 0307 added F9 save command - 885 bytes
;; 0308 add dirty file protection - 908 bytes
;; 0309 add print from WINEXEC - 965 bytes
;; 0400 add reverse search - 994 bytes
;; 0401 re-org for better cmprss - 990 bytes
;; 0402 external font patch tail - 988 bytes
;; 0403 and 044 crinkler fold - 980 bytes
;; 0404 15-byte font face slot - discarded
;; 0405 restore 20-byte font - 980 bytes
;; 0406 window state tail - 984 bytes
;; 0407 pack state with height - state failed
;; 0408 startup syscommand tail - 987 bytes

```

Opening an existing file:

Drag and drop it onto DTE.

Creating a new file:

Double-click DTE to run it. A new file "f" will be automatically created. If f already exists, then DTE simply opens that. Edit the new file and Save. Quit DTE and rename f to whatever you want.

Saving a file:

Press F9 or click the System Menu->Save. There is no "Save-As".

Closing DTE

DTE now has unsaved-file protection. If the file is unsaved (* appended to the name in the title bar), the GUI "X" and the System Menu "Close" (or Alt-F4) do nothing. They are only enabled if a file is unchanged since last save.

X! (X bang) in the system menu overrides the unsaved protection and allows the user to "throw away changes".

Searching the file

Highlight any text in the file and press F3 to search forwards or F2 to search backwards. DTE will highlight each next found instance for every F2 or F3 keypress. End of file and beginning of file both silently wrap to the other end.

One-time Replace

DTE has no Replace dialog, but a quick one-time replace is available. Copy the replacement text to the Windows clipboard, highlight the text to find, and use F2 or F3 to move to the desired instance. Press Ctrl+Q and the highlighted instance is immediately replaced.

Printing a file

F12 immediately prints to the active (default) printer. If the active printer is PDF, a dialog will open to choose a file name to save as. This is a trick. DTE is actually calling Notepad with the /p flag. The user only briefly sees the Notepad "Now printing" dialog. The Notepad editor never appears. Note: F12 is disabled unless the file has been saved.

DTE_SETUP

Place DTE_SETUP.exe beside dte.exe and run it to change DTE's font and startup state. First choose a font. Then choose whether DTE should start Windowed or Maximized.

The selected settings are written directly into dte.exe. No INI file or Registry settings are used. Font names may contain up to 19 characters. Longer font names are refused. Running DTE_SETUP expands the configured dte.exe to 1024 bytes.

Word Wrap

Word wrap is always on.

Keyboard Navigation

Arrow keys:	Move cursor in that direction
Home	Start of line
End	End of line
Ctrl + Home	Top of file
Ctrl + End	End of file
Page Up	Scroll up
Page Down	Scroll down
Ctrl + Left	Move to previous word
Ctrl + Right	Move to next word

Selection

Shift + Arrow	Extend selection
Shift + Home	Select to start of line
Shift + End	Select to end of line
Ctrl + Shift + Home	Select to top of file
Ctrl + Shift + End	Select to end of file
Ctrl + A	Select all
L/Click & Drag	All of the above

Editing

Backspace	Delete character before cursor
Delete	Delete character at cursor
Ctrl + Backspace	Delete previous word
Ctrl + Delete	Delete next word
Enter	Insert newline

Clipboard:

Ctrl + C	Copy
Ctrl + Insert	Copy
Ctrl + X	Cut
Shift + Delete	Cut
Ctrl + V	Paste
Shift + Insert	Paste

Undo / Redo:

Ctrl + Z	undo
Ctrl + Y	redo

Right-Click Editor Menu:

Disabled. Use keyboard commands.

System Menu

Can be accessed by upper left icon or
by r/click anywhere in the title bar.

DTE Max Editable File Size

100 MB files verified as working.

This user manual, and major portions
of DTE itself, were written with DTE.

/// // // // // // //
// // D T E // // //

<https://github.com/mpower-codeworks/Daves-Tiny-Editor>