

INSTALLATION OF NESSUS TOOL

INSTALLATION

STEP 1 : Go to tenable.com to download the latest version of Nessus tool. Choose the platform in accordance with your hardware and click on “Download”.



STEP 2: Now in the terminal switch to root user and change directory(cd) to Downloads and type ls to list all the downloaded files. Here look for Nessus tool which you downloaded.

```
root@kali: /home/mubassherazaidy/Downloads
Session Actions Edit View Help
(mubassherazaidy@kali)~]
$ sudo su
[sudo] password for mubassherazaidy:
(root@kali)~ /home/mubassherazaidy]
$ cd Downloads
(root@kali)~ /home/mubassherazaidy/Downloads]
$ ls
burpsuite_pro_linux_v2025_9_5.sh  kali-linux-2024.4-installer-arm64.is  Nessus-10.10.1-ubuntu1804_aarch64.deb  SHA256SUMS
cacert.der                      kali-linux-2024.4-installer-arm64.iso  newtext.txt
```

STEP 3 : Execute the following command to install Nessus tool : `sudo dpkg -i Nessus-10.10.1-ubuntu1804_aarch64.deb`

```
(root@kali)~/home/mubassherazaaidy/Downloads
# sudo dpkg -i Nessus-10.10.1-ubuntu1804_aarch64.deb
Selecting previously unselected package nessus.
(Reading database ... 421659 files and directories currently installed.)
Preparing to unpack Nessus-10.10.1-ubuntu1804_aarch64.deb ...
Unpacking nessus (10.10.1) ...
Setting up nessus (10.10.1) ...
HMAC : (Module_Integrity) : Pass
SHA1 : (KAT_Digest) : Pass
SHA2 : (KAT_Digest) : Pass
SHA3 : (KAT_Digest) : Pass
TDES : (KAT_Cipher) : Pass
AES_GCM : (KAT_Cipher) : Pass
AES_ECB_Decrypt : (KAT_Cipher) : Pass
RSA : (KAT_Signature) : RNG : (Continuous_RNG_Test) : Pass
Pass
ECDSA : (PCT_Signature) : Pass
ECDSA : (PCT_Signature) : Pass
DSA : (PCT_Signature) : Pass
TLS13_KDF_EXTRACT : (KAT_KDF) : Pass
TLS13_KDF_EXPAND : (KAT_KDF) : Pass
TLS12_PR_F : (KAT_KDF) : Pass
PBKDF2 : (KAT_KDF) : Pass
SSHKDF : (KAT_KDF) : Pass
KBKDF : (KAT_KDF) : Pass
HKDF : (KAT_KDF) : Pass
SSKDF : (KAT_KDF) : Pass
X963KDF : (KAT_KDF) : Pass
X942KDF : (KAT_KDF) : Pass
HASH : (DRBG) : Pass
CTR : (DRBG) : Pass
HMAC : (DRBG) : Pass
DH : (KAT_KA) : Pass
ECDH : (KAT_KA) : Pass
RSA_Encrypt : (KAT_AsymmetricCipher) : Pass
RSA_Decrypt : (KAT_AsymmetricCipher) : Pass
RSA_Decrypt : (KAT_AsymmetricCipher) : Pass
INSTALL PASSED
Unpacking Nessus Scanner Core Components...

- You can start Nessus Scanner by typing /bin/systemctl start nessusd.service
- Then go to https://NESSUS_HOSTNAME_OR_IP:8834/ to configure your scanner
```


STEP 4 : Now run the following command to start Nessus tool : `systemctl start nessusd`

- To check the status of Nessus run the following command : `systemctl status nessusd`

```
TLS13_KDF_EXPAND : (KAT_KDF) : Pass
TLS12_PRF : (KAT_KDF) : Pass
PBKDF2 : (KAT_KDF) : Pass
SSHKDF : (KAT_KDF) : Pass
KBKDF : (KAT_KDF) : Pass
HKDF : (KAT_KDF) : Pass
SSKDF : (KAT_KDF) : Pass
X963KDF : (KAT_KDF) : Pass
X942KDF : (KAT_KDF) : Pass
HASH : (DRBG) : Pass
CTR : (DRBG) : Pass
HMAC : (DRBG) : Pass
DH : (KAT_KA) : Pass
ECDH : (KAT_KA) : Pass
RSA_Encrypt : (KAT_AsymmetricCipher) : Pass
RSA_Decrypt : (KAT_AsymmetricCipher) : Pass
RSA_Decrypt : (KAT_AsymmetricCipher) : Pass
INSTALL PASSED
Unpacking Nessus Scanner Core Components...



- You can start Nessus Scanner by typing /bin/systemctl start nessusd.service
- Then go to https://NESSUS_HOSTNAME_OR_IP:8834/ to configure your scanner

[root@kali]~/home/mubassherazaidy/Downloads
# sudo systemctl start nessusd


[root@kali]~/home/mubassherazaidy/Downloads
# sudo systemctl status nessusd
● nessusd.service - The Nessus Vulnerability Scanner
   Loaded: loaded (/usr/lib/systemd/system/nessusd.service; disabled; preset: disabled)
   Active: active (running) since Mon 2025-11-10 21:57:25 IST; 14s ago
 Invocation: 48e8a5ffe79e4fe185da6c9e24c19d8b
   Main PID: 9653 (nessus-service)
    Tasks: 14 (limit: 7989)
  Memory: 163.7M (peak: 163.7M)
     CPU: 14.301s
   CGroup: /system.slice/nessusd.service
           └─9653 /opt/nessus/sbin/nessus-service -q
             └─9655 nessusd -q

Nov 10 21:57:25 kali systemd[1]: Started nessusd.service - The Nessus Vulnerability Scanner.
Nov 10 21:57:25 kali nessus-service[9653]: nessus-service [9653][INFO] : Nessus 19.15.1 [build 20010] Started
```


STEP 5 : Next in your browser type <https://localhost:8834> . This will Bring you to the nessus sign up page.



STEP 6 : Now in your browser type Nessus essentials and click on “Tenable Nessus Essentials Vulnerability Scanner” from www.tenable.com



STEP 7 : Enter your credentials and click on “Get Started”.



Tenable Nessus® Essentials

Nessus Essentials is a free product from Tenable that provides high-speed, in-depth vulnerability scanning for up to 16 IP addresses per scanner.

Limitations: Nessus Essentials does not support unlimited scanning, compliance checks, content audits, Live Results, configurable reports, or the Nessus virtual appliance. For access to these features and more, [upgrade to Nessus Professional](#).

For Students & Educators: If you're using Nessus Essentials for education, register through the [Tenable for Education](#) program to get started.

Learn Nessus: Our [on-demand Nessus Fundamentals course](#) covers everything from asset discovery to compliance, helping you master Nessus for effective vulnerability assessment in various business use cases.

Register for an Activation Code

You are registering for a 1-year Nessus Essentials license.


First Name Last Name

Business Email


☐ Check to receive updates from Tenable
Tenable will only process your personal data in accordance with its [Privacy Policy](#).

Get Started

STEP 8 : On your registered email you will get an Activation Code, save/copy it.



STEP 9 : Now come back to the Nessus essentials website and click on “Continue”.



STEP 10:: Create a user account, create a username and password and click on "Submit".



 **tenable**
Nessus

Create a user account

Create a Nessus administrator user account. Use this username and password to log in to Nessus.

Username *

Password *


 

[Back](#) [Submit](#)

© 2025 Tenable®, Inc.



STEP 11 : Once the initialisation is completed enter your credentials and click on "Sign In"



- We have successfully installed Nessus tool.

