


CNET Lab 11

Network topology diagram



Task 1:

Messages:

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC0	PC7	ICMP		0.000	N	0	(edit)	(delete)
	Successful	PC2	PC5	ICMP		0.000	N	1	(edit)	(delete)
	Successful	PC0	PC7	ICMP		0.000	N	2	(edit)	(delete)
	Successful	PC4	PC0	ICMP		0.000	N	3	(edit)	(delete)

CLI:

```

Router(config)#router ospf 10
Router(config-router)#network 162.25.0.0 0.0.255.255 area 3
Router(config-router)#network 162.29.0.0 0.0.255.255 area 3
Router#en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router ospf 10
Router(config-router)#network 162.23.0.0 0.0.255.255 area1
^
% Invalid input detected at '^' marker.
Router(config-router)#network 162.23.0.0 0.0.255.255 area 1
Router(config-router)#network 162.26.0.0 0.0.255.255 area 1

```

```

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/
Z.
Router(config)#network ospf 10
      ^
% Invalid input detected at '^' marker.

Router(config)#router ospf 10
Router(config-router)#network 162.27.0.0 0.0.255.255 area 2
Router(config-router)#network 162.24.0.0 0.0.255.255 area 2
Router(config-router)#network 162.28.0.0 0.0.255.255 area 2
-

```

Routing Table:

Routing Table for Router0				
Type	Network	Port	Next Hop IP	Metric
O	162.25.0.0/16	Serial2/0	162.26.0.2	110/193
C	162.26.0.0/16	Serial2/0	---	0/0
O	162.27.0.0/16	Serial2/0	162.26.0.2	110/128
O	162.28.0.0/16	Serial2/0	162.26.0.2	110/192
Routing Table for Router2				
Type	Network	Port	Next Hop IP	Metric
O	162.23.0.0/16	Serial2/0	162.27.0.2	110/129
C	162.24.0.0/16	FastEthernet0/0	---	0/0
O	162.25.0.0/16	Serial3/0	162.28.0.2	110/129
O	162.26.0.0/16	Serial2/0	162.27.0.2	110/128

TASK 2:

Messages:

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC0	PC3	ICMP		0.000	N	0	(edit)	(delete)
	Successful	PC1	PC5	ICMP		0.000	N	1	(edit)	(delete)
	Successful	PC6	PC1	ICMP		0.000	N	2	(edit)	(delete)

CLI:

```

Router>en
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router eigrp 10
Router(config-router)#network 162.24.0.0 0.0.255.255
Router(config-router)#network 162.27.0.0 0.0.255.255
Router(config-router)#network 162.28.0.0 0.0.255.255

Router>en
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router eigrp 10
Router(config-router)#network 162.25.0.0 0.0.255.255
Router(config-router)#network 162.29.0.0 0.0.255.255

Router>en
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#router eigrp 10
Router(config-router)#network 162.26.0.0 0.0.255.255
Router(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 10: Neighbor 162.26.0.1
(Serial2/0) is up: new adjacency
network 162.27.0.0 0.0.255.255
Router(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 10: Neighbor 162.27.0.1
(Serial3/0) is up: new adjacency
network 162.30.0.0 0.0.255.255
Router(config-router)#exit
Router(config)#router eigrp 10
Router(config-router)#network 162.26.0.0 0.0.255.255 area 1
                                     ^
% Invalid input detected at '^' marker.

Router(config-router)#network 162.26.0.0 0.0.255.255
Router(config-router)#network 162.23.0.0 0.0.255.255

```

Routing Table:

Routing Table for Router0					Routing Table for Router2				
Type	Network	Port	Next Hop IP	Metric	Type	Network	Port	Next Hop IP	Metric
C	162.23.0.0/16	FastEthernet0/0 ---	---	0/0	D	162.23.0.0/16	Serial2/0	162.27.0.2 90/21026560	
D	162.24.0.0/16	Serial2/0	162.26.0.2 90/21026560		C	162.24.0.0/16	FastEthernet0/0 ---	---	0/0
D	162.25.0.0/16	Serial2/0	162.26.0.2 90/21538560		D	162.25.0.0/16	Serial3/0	162.28.0.2 90/21026560	
C	162.26.0.0/16	Serial2/0 ---	---	0/0	D	162.26.0.0/16	Serial2/0	162.27.0.2 90/21024000	

Routing Table for Router1					Routing Table for Router3				
Type	Network	Port	Next Hop IP	Metric	Type	Network	Port	Next Hop IP	Metric
D	162.23.0.0/16	Serial2/0	162.26.0.1 90/20514560		D	162.23.0.0/16	Serial6/0	162.30.0.1 90/21026560	
D	162.24.0.0/16	Serial3/0	162.27.0.1 90/20514560		D	162.24.0.0/16	Serial2/0	162.28.0.1 90/20514560	
D	162.25.0.0/16	Serial6/0	162.30.0.2 90/21026560		D	162.25.0.0/16	Serial3/0	162.29.0.1 90/20514560	
C	162.26.0.0/16	Serial2/0 ---	---	0/0	D	162.26.0.0/16	Serial6/0	162.30.0.1 90/21024000	

Routing Table for Router4				
Type	Network	Port	Next Hop IP	Metric
D	162.23.0.0/16	Serial2/0	162.29.0.2 90/21538560	
D	162.24.0.0/16	Serial2/0	162.29.0.2 90/21026560	
C	162.25.0.0/16	FastEthernet0/0 ---	---	0/0
D	162.26.0.0/16	Serial2/0	162.29.0.2 90/21536000	

