


# CNET Lab 8

## Part a:



## Part b:

```
Router(config-if)#en
% Ambiguous command: "en"
Router(config)#config t
%Invalid hex value
Router(config)#interface fastEthernet0/0
Router(config-if)#add ip 192.168.10.1 255.255.255.0
^
% Invalid input detected at '^' marker.

Router(config-if)#ip add 192.168.10.1 255.255.255.0
Router(config-if)#no shut
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet1/0
Router(config-if)#exit
Router(config)#interface FastEthernet1/0
Router(config-if)#ip add 192.168.100.1 255.255.255.0
Router(config-if)#exit
```

## Part c:

```

Router#en
Router#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#ip route 192.168.20.0 255.255.255.0 192.168.100.2
Router(config)#ip route 192.168.30.0 255.255.255.0 192.168.200.2
Router(config)#show ip route
      ^
% Invalid input detected at '^' marker.

Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C     192.168.10.0/24 is directly connected, FastEthernet0/0
S     192.168.20.0/24 [1/0] via 192.168.100.2
C     192.168.100.0/24 is directly connected, FastEthernet1/0

Router(config)#ip route 192.168.30.0 255.255.255.0 192.168.200.2
Router(config)#ip route 192.168.10.0 255.255.255.0 192.168.100.1
Router(config)#exit

```

```

Router#en
Router#config
Configuring from terminal, memory, or network [terminal]? terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#ip route 192.168.20.0 255.255.255.0 192.168.200.1
Router(config)#ip route 192.168.10.0 255.255.255.0 192.168.100.1
Router(config)#exit

```

## Part d:

| Fire                                                                                | Last Status | Source   | Destination | Type | Color                                                                               | Time(sec) | Periodic | Num | Edit   | Delete   |
|-------------------------------------------------------------------------------------|-------------|----------|-------------|------|-------------------------------------------------------------------------------------|-----------|----------|-----|--------|----------|
|  | Successful  | Head-... | Dev-PC0     | ICMP |  | 0.000     | N        | 0   | (edit) | (delete) |
|  | Successful  | Dev-P... | Sales-PC0   | ICMP |  | 0.000     | N        | 1   | (edit) | (delete) |
|  | Successful  | Sales... | Head-PC0    | ICMP |  | 0.000     | N        | 2   | (edit) | (delete) |